

# GnuCOBOL Manual

---

for GnuCOBOL 3.1

**Keisuke Nishida, Roger While, Brian Tiffin, Simon Sobisch**

Edition 3.1

Updated for GnuCOBOL 3.1

10 November 2020

GnuCOBOL (formerly OpenCOBOL) is a free COBOL compiler and runtime. `cobc` translates COBOL source to executable using intermediate C together with a designated C compiler and linker. `cobcrun` is a module loader to run generated modules, `libcob` provides the necessary runtime.

This manual corresponds to GnuCOBOL 3.1.

---

Copyright © 2002-2012, 2014-2020 Free Software Foundation, Inc.

Written by Keisuke Nishida, Roger While, Brian Tiffin, Simon Sobisch.

Permission is granted to make and distribute verbatim copies of this manual provided the copyright notice and this permission notice are preserved on all copies.

Permission is granted to copy and distribute modified versions of this manual under the conditions for verbatim copying, provided that the entire resulting derived work is distributed under the terms of a permission notice identical to this one.

Permission is granted to copy and distribute translations of this manual into another language, under the above conditions for modified versions, except that this permission notice may be stated in a translation approved by the Free Software Foundation.

# Table of Contents

<b>1</b>	<b>Getting started</b> .....	<b>1</b>
1.1	Hello, world! .....	1
<b>2</b>	<b>Compile</b> .....	<b>2</b>
2.1	Compiler options .....	2
2.1.1	Help options .....	2
2.1.2	Build target .....	2
2.1.3	Source format .....	3
2.1.4	Warning options .....	4
2.1.5	Configuration options .....	5
2.1.6	Listing options .....	7
2.1.7	Debug switches .....	8
2.1.8	Miscellaneous .....	9
2.2	Multiple sources .....	9
2.2.1	Static linking .....	9
2.2.2	Dynamic linking .....	10
2.2.2.1	Driver program .....	10
2.2.2.2	Compiling programs separately .....	10
2.2.3	Building library .....	11
2.2.4	Using library .....	11
2.3	C interface .....	11
2.3.1	Writing Main Program in C .....	11
2.3.2	Static linking with COBOL programs .....	12
2.3.3	Dynamic linking with COBOL programs .....	13
2.3.4	Static linking with C programs .....	13
2.3.5	Dynamic linking with C programs .....	14
2.3.6	Redirecting output to a (FILE *) .....	14
<b>3</b>	<b>Customize</b> .....	<b>16</b>
3.1	Customizing compiler .....	16
3.2	Customizing library .....	16
<b>4</b>	<b>Optimize</b> .....	<b>17</b>
4.1	Optimize options .....	17
4.2	Optimize call .....	17
4.3	Optimize binary .....	17
<b>5</b>	<b>Debug</b> .....	<b>18</b>
5.1	Debug options .....	18
<b>6</b>	<b>Non-standard extensions</b> .....	<b>19</b>
6.1	SELECT ASSIGN TO .....	19
6.1.1	Literal file .....	19
6.1.2	<variable> .....	19
6.1.3	<environment variable> .....	19
6.2	Indexed file packages .....	19

6.3	Extended ACCEPT statement .....	19
6.3.1	LINE .....	20
6.3.2	COLUMN .....	20
6.3.3	AUTO-SKIP .....	20
6.3.4	BACKGROUND-COLOR .....	20
6.3.5	BELL .....	20
6.3.6	BLINK .....	20
6.3.7	FOREGROUND-COLOR .....	20
6.3.8	LOWLIGHT .....	20
6.3.9	PROMPT .....	20
6.3.10	PROTECTED .....	20
6.3.11	SIZE .....	21
6.3.12	UPDATE .....	21
6.3.13	ON EXCEPTION .....	21
6.3.14	NOT ON EXCEPTION .....	21
6.4	ACCEPT special keys .....	21
6.4.1	Arrow keys .....	21
6.4.2	Backspace key .....	21
6.4.3	Delete keys .....	21
6.4.4	End key .....	22
6.4.5	Home key .....	22
6.4.6	Insert key .....	22
6.4.7	Tab keys .....	22
6.5	Extended DISPLAY statement .....	22
6.5.1	BELL .....	22
6.5.2	BLANK .....	22
6.5.3	ERASE .....	23
6.5.4	SIZE .....	23
6.5.5	Figurative Constants .....	23
6.6	CONTENT-LENGTH .....	23
6.7	CONTENT-OF .....	24
<b>7</b>	<b>System Routines .....</b>	<b>25</b>
7.1	CBL_GC_GETOPT .....	25
7.2	CBL_GC_HOSTED .....	26
7.3	CBL_GC_NANOSLEEP .....	29
7.4	CBL_GC_FORK .....	29
7.5	CBL_GC_WAITPID .....	30
<b>Appendix A</b>	<b>Compiler cobc options .....</b>	<b>31</b>
A.1	Common Options .....	31
A.2	Warning options .....	32
A.3	Compiler options .....	34
A.4	Compiler dialect configuration options .....	36
<b>Appendix B</b>	<b>Reserved Words .....</b>	<b>42</b>
B.1	Common reserved words .....	42
B.2	Extra (obsolete) context sensitive words .....	60
B.3	Internal registers .....	60
<b>Appendix C</b>	<b>Intrinsic Functions .....</b>	<b>61</b>

<b>Appendix D</b>	<b>System routines</b> .....	<b>64</b>
<b>Appendix E</b>	<b>System names</b> .....	<b>66</b>
E.1	System names: device .....	66
E.2	System names: feature .....	66
E.3	System names: switch .....	66
<b>Appendix F</b>	<b>Compiler Configuration</b> .....	<b>67</b>
<b>Appendix G</b>	<b>Module loader cobcrun options</b> .....	<b>73</b>
<b>Appendix H</b>	<b>Runtime configuration</b> .....	<b>74</b>
H.1	General instructions .....	74
H.2	General environment .....	75
H.3	File I/O .....	77
H.4	Screen I/O .....	78
H.5	Report I/O .....	81
<b>Appendix I</b>	<b>GNU Free Documentation License</b> .....	<b>82</b>

# 1 Getting started

## 1.1 Hello, world!

This is a sample program that displays “Hello, world!”:

```

---- hello.cob -----
      * Sample COBOL program
      IDENTIFICATION DIVISION.
      PROGRAM-ID. hello.
      PROCEDURE DIVISION.
      DISPLAY "Hello, world!".
      STOP RUN.
-----

```

The compiler, `cobc`, is executed as follows:

```

$ cobc -x hello.cob
$ ./hello
Hello, world!

```

The executable file name (`hello` in this case) is determined by removing the extension from the source file name.

You can specify the executable file name by specifying the compiler option `-o` as follows:

```

$ cobc -x -o hello-world hello.cob
$ ./hello-world
Hello, world!

```

The program can be written in a more modern style, with free format code, inline comments, the `GOBACK` verb and an optional `END-DISPLAY` terminator:

```

---- hellonew.cob -----
*> Sample GnuCOBOL program
identification division.
program-id. hellonew.
procedure division.
display
    "Hello, new world!"
end-display
goback.
-----

```

To compile free-format code, you must use the compiler option `-free`.

```

$ cobc -x -free hellonew.cob
$ ./hellonew
Hello, new world!

```

## 2 Compile

This chapter describes how to compile COBOL programs using GnuCOBOL.

### 2.1 Compiler options

The compiler `cobc` accepts the options described in this section. The compiler arguments follow the general syntax `cobc options file [file ...]`. A complete list of options can be displayed by using the option `--help`.

#### 2.1.1 Help options

The following switches display information about the compiler:

`--help, -h`

Display help screen (see Appendix A [Appendix A], page 31). No further actions will be taken.

`--version`

Display compiler version, author package date and executable build date. `-V` will also display version. No further actions will be taken.

`--info`

Display build information along with the default and current compiler configurations. No further actions will be taken except for further display options.

`--version, -v`

Verbosely display the programs invoked during compilation and additional diagnostics. Use multiple times to increase the verbosity.

`--list-reserved`

Display reserved words (see Appendix B [Appendix B], page 42). A Yes/No output shows if the word is supported<sup>1</sup>, context sensitive and its aliases. The given options for reserved words specified for example by option `-std=dialect` will be taken into account. No further actions will be taken except for further display options.

`--list-intrinsics`

Display intrinsic functions (see Appendix C [Appendix C], page 61). A Y/N field shows if the function is implemented. No further actions will be taken except for further display options.

`--list-system`

Display system routines (see Appendix D [Appendix D], page 64). No further actions will be taken except for further display options.

`--list-mnemonics`

Display mnemonic names (see Appendix E [Appendix E], page 66). No further actions will be taken except for further display options.

#### 2.1.2 Build target

The compiler `cobc` treats files like `*.cob`, `*.cbl` as COBOL source code, `*.c` as C source code, `*.o` as object code, `*.i` as preprocessed code and `*.so` as dynamic modules and knows how to handle such files in the generation, compilation, and linking steps.

The special input name `-` takes input from `stdin` which is assumed to be COBOL source, and uses a default output name of `a.out` (or `a.so/c/o/i`, selected as appropriate) for the build type.

---

<sup>1</sup> Support may be partial or complete.

By default, the compiler builds a dynamically loadable module.

The following options specify the target type produced by the compiler:

- E        Preprocess only: compiler directives are executed, comment lines are removed and COPY statements are expanded. The output is saved in file *\*.i*.
- C        Translation only. COBOL source files are translated into C files. The output is saved in file *\*.c*.
- S        Compile only. Translated C files are compiled by the C compiler to assembler code. The output is saved in file *\*.s*.
- c        Compile and assemble. This is equivalent to `cc -c`. The output is saved in file *\*.o*.
- m        Compile, assemble, and build a dynamically loadable module (i.e., a shared library). The output is saved in file *\*.so*.<sup>2</sup> This is the default behaviour.
- b        Compile, assemble, and combine all input files into a single dynamically loadable module. Unless `-o` is also used, the output is saved using the first filename as *\*.so*.
- x        Include the main function in the output, creating an executable image. The main entry point being the first program in the file.  
  
This option takes effect at the translation stage. If you give this option with `-C`, you will see the main function at the end of the generated C file.
- j, -job, -j=*args*, -job=*args*  
Run job after compilation. Either from executable with `-x`, or with `cobcrun` when compiling a module. Optional arguments *args*, if given, are passed to the program or module command line.
- I *directory*  
Add *directory* to copy/include search path.
- L *directory*  
Add *directory* to library search path.
- l *lib*    Link the library *lib*.
- D *define* Pass *define* to the COBOL compiler.
- o *file*    Place the output into *file*.

### 2.1.3 Source format

GnuCOBOL supports both fixed and free source format. The default format is the fixed format. This can be overridden either by the `>>SOURCE [FORMAT] [IS] {FIXED|FREE}` directive, or by one of the following options:

- free, -F    Free format. The program-text area starts in column 1 and continues till the end of line (effectively 255 characters in GnuCOBOL).
- fixed      Fixed format. Source code is divided into: columns 1-6, the sequence number area; column 7, the indicator area; columns 8-72, the program-text area; and columns 72-80 as the reference area.<sup>3</sup>

---

<sup>2</sup> The extension varies depending on your host.

<sup>3</sup> Historically, fixed format was based on 80-character punch cards.

### 2.1.4 Warning options

Warnings are diagnostic messages that report constructions that are not inherently erroneous but that are risky or suggest there may have been an error.

The following options do not enable specific warnings but control the kinds of diagnostics produced by `cobc`.

`-fsyntax-only`

Check the code for syntax errors, but don't do anything beyond that.

`-fmax-errors=n`

Limits the maximum number of error messages to *n*, at which point `cobc` bails out rather than attempting to continue processing the source code. If *n* is 0, there is no limit on the number of error messages produced. If `-Wfatal-errors` is also specified, then `-Wfatal-errors` takes precedence over this option.

`-w`

Inhibit all warning messages.

`-Werror` Make all warnings into errors.

`-Werror=warning`

Make the specified *warning* into an error. The specifier for a warning is appended; for example `-Werror=obsolete` turns the warnings controlled by `-Wobsolete` into errors. This switch takes a negative form, to be used to negate `-Werror` for specific warnings; for example `-Wno-error=obsolete` makes `-Wobsolete` warnings not be errors, even when `-Werror` is in effect.

Note that specifying `-Werror=foo` automatically implies `-Wfoo`. However, `-Wno-error=foo` does not imply anything.

`-Wfatal-errors`

This option causes the compiler to abort compilation on the first error occurred rather than trying to keep going and printing further error messages.

You can request many specific warnings with options beginning with '`-W`', for example `-Wimplicit-define` to request warnings on implicit declarations. Each of these specific warning options also has a negative form beginning '`-Wno`' to turn off warnings; for example, `-Wno-implicit-define`. This manual lists only one of the two forms, whichever is not the default.

Some options, such as `-Wall` and `-Wextra`, turn on other options, such as `-Wtruncate`. The combined effect of positive and negative forms is that more specific options have priority over less specific ones, independently of their position in the command-line. For options of the same specificity, the last one takes effect.

`-Wall` Enable all the warnings about constructions that some users consider questionable, and that are easy to avoid (or modify to prevent the warning).

The list of warning flags turned on by this option is shown in `--help`.

`-Wextra, -W`

Enable every possible warning that is not dialect specific. This includes more information than `-Wall` would normally provide.

(This option used to be called `-W`. The older name is still supported, but the newer name is more descriptive.)

`-Wwarning`

Enable single warning *warning*.

`-Wno-warning`

Disable single warning *warning*.

- Warchaic**  
Warn if archaic features are used, such as continuation lines or the `NEXT SENTENCE` statement.
- Wcall-params**  
Warn if non-01/77-level items are used as arguments in a `CALL` statement. This is *not* set with `-Wall`.
- Wcolumn-overflow**  
Warn if text after column 72 in `FIXED` format. This is *not* set with `-Wall`.
- Wconstant**  
Warn inconsistent constant
- Wimplicit-define**  
Warn if implicitly defined data items are used.
- Wlinkage**  
Warn dangling `LINKAGE` items. This is *not* set with `-Wall`.
- Wobsolete**  
Warn if obsolete features are used.
- Wparentheses**  
Warn about any lack of parentheses around `AND` within `OR`.
- Wredefinition**  
Warn about incompatible redefinitions of data items.
- Wstrict-typing**  
Warn about type mismatch strictly.
- Wterminator**  
Warn about the lack of scope terminator `END-XXX`. This is *not* set with `-Wall`.
- Wtruncate**  
Warn on possible field truncation. This is *not* set with `-Wall`.
- Wunreachable**  
Warn if statements are unreachable. This is *not* set with `-Wall`.
- Wadditional**  
Enable warnings that don't have an own warning flag.

### 2.1.5 Configuration options

The compiler uses many dialect specific options. These may be set via a defined dialect by `-std=`, a configuration file by `-conf=` or by using the single dialect flags directly.

See Appendix F [Compiler Configuration], page 67, and `config/*.conf`.

Note concerning the defined dialects: The GnuCOBOL compiler tries to limit both the feature-set and reserved words to the specified compiler when the "strict" dialects are used. COBOL sources compiled with these dialects are therefore *likely* to compile with the specified compiler and vice versa: sources that were compiled on the specified compiler should compile without any issues with GnuCOBOL.

With the "non-strict" dialects GnuCOBOL will activate the complete feature-set where it doesn't directly conflict with the specified dialect, including reserved words. COBOL sources compiled with these dialects therefore may work only with GnuCOBOL. COBOL sources may need a change because of reserved words in GnuCOBOL, otherwise offending words `word-1` and `word-2` may be removed by `-fno-reserved=word-1,word-1`.

The dialects COBOL-85, X/Open COBOL, COBOL 2002 and COBOL 2014 are always "strict".

**-std=diaclect**

Compiler uses the given *diaclect* to determine certain compiler features and warnings.

**-std=default**

GnuCOBOL dialect, supporting many of the COBOL 2002 and COBOL 2014 features, many extensions found in other dialects and its own feature-set

**-std=cobol85**

COBOL-85 without any extensions other than the amendment Intrinsic Function Module (1989), source compiled with this dialect is likely to compile with most COBOL compilers

**-std=xopen**

X/Open COBOL (based on COBOL-85) without any vendor extensions, source compiled with this dialect is likely to compile with most COBOL compilers; will warn items that "should not be used in a conforming X/Open COBOL source program"

**-std=cobol2002, -std=cobol2014**

COBOL 2002 / COBOL 2014 without any vendor extensions, use **-Warchaic** and **-Wobsolete** if archaic/obsolete features should be flagged

**-std=ibm-strict, -std=ibm**

IBM compatible

**-std=mvs-strict, -std=mvs**

MVS compatible

**-std=mf-strict, -std=mf**

Micro Focus compatible

**-std=bs2000-strict, -std=bs2000**

BS2000 compatible

**-std=acu-strict, -std=acu**

ACUCOBOL-GT compatible

**-std=rm-strict, -std=rm**

RM/COBOL compatible

**-std=realia-strict, -std=realia**

CA Realia II compatible

**-freserved-words=diaclect**

Compiler uses the given *diaclect* to determine the reserved words.

**-conf=<file>**

User-defined dialect configuration.

You can override each single configuration entry by using compiler configuration options on the command line.

Examples:

**-frelax-syntax-checks**

**-frenames-uncommon-levels=warning**

**-fnot-reserved=CHAIN,SCREEN**

**-ftab-width=4**

See Appendix A [Compiler `cobc` options], page 31.

## 2.1.6 Listing options

- `-t=file`   Generate and place the standard print listing into *file*.
- `-T=file`   Generate and place a wide print listing into *\*file*.
- `--tlines=lines`  
Specify lines per page in print listing, default = 55. Set to zero for no additional page breaks.
- `-ftsymbols`  
Generate symbol table in listing.
- `-fno-theader`  
Suppress all headers from listing while keeping page breaks.
- `-fno-tmessages`  
Suppress warning and error summary from listing.
- `-fno-tsource`  
Suppress actual source from listing (for example to only produce the cross-reference).
- `-P, -Pdirectory, -P=file`  
Generate and place a preprocessed listing (old format) into *filename.lst*, *directory/filename.lst*, *file*.
- `-Xref`
- `-X`       Generate cross reference in the listing.

Here is an example program listing with the options `-t -ftsymbols`:

```

GnuCOBOL 3.0.0  test.cbl                               Mon May 14 10:23:45 2018  Page 0001

LINE  PG/LN  A...B.....
000001      IDENTIFICATION  DIVISION.
000002      PROGRAM-ID.      prog.
000003      ENVIRONMENT DIVISION.
000004      CONFIGURATION SECTION.
000005      DATA              DIVISION.
000006      WORKING-STORAGE SECTION.
000007      COPY 'values.cpy'.
00001C      78 I  VALUE 20.
00002C      78 J  VALUE 5000.
00003C      78 M  VALUE 5.
000008      01 SETUP-REC.
000009          05 FL1          PIC X(04).
000010          05 FL2          PIC ZZZZ.
000011          05 FL3          PIC 9(04).
000012          05 FL4          PIC 9(08) COMP.
000013          05 FL5          PIC 9(04) COMP-4.
000014          05 FL6          PIC Z,ZZZ.99.
000015          05 FL7          PIC S9(05) SIGN LEADING SEPARATE.
000016          05 FL8          PIC X(04).
000017          05 FL9 REDEFINES FL8 PIC 9(04).
000018          05 FLA.
000019              10 FLB OCCURS I TIMES.
000020                  15 FLC PIC X(02).
000021              10 FLD PIC X(20).
000022          05 FLD1          PIC X(100).
000023          05 FLD2 OCCURS M TO J TIMES DEPENDING ON FL5.
000024              10 FILLER PIC X(01).
000025          05 FLD3          PIC X(3).
000026          05 FLD4          PIC X(4).
000027      PROCEDURE          DIVISION.
```

```
000028          STOP RUN.
```

The first part of the listing lists the program text. If the program text is a COPY the line number reflects the COPY line number and is appended with a 'C'.

When the wide list option `-T` is specified, the `SEQUENCE` columns (for fixed-form reference-format) are included in the listing.

The second part of the listing file is the listing of the Symbol Table:

```
GnuCOBOL 3.0.0  test.cbl          Mon May 14 10:23:45 2018  Page 0002

SIZE TYPE          LVL  NAME          PICTURE

5204 GROUP          01   SETUP-REC
0004 ALPHANUMERIC  05   FL1          X(04)
0005 ALPHANUMERIC  05   FL2          ZZZZ
0004 ALPHANUMERIC  05   FL3          9(04)
0004 NUMERIC        05   FL4          9(08) COMP
0002 NUMERIC        05   FL5          9(04) COMP
0008 ALPHANUMERIC  05   FL6          Z,ZZZ.99
0006 ALPHANUMERIC  05   FL7          S9(05)
0004 ALPHANUMERIC  05   FL8          X(04)
0004 ALPHANUMERIC-R 05   FL9          9(04)
0060 ALPHANUMERIC  05   FLA
0040 ALPHANUMERIC  10   FLB          OCCURS 20
0002 ALPHANUMERIC  15   FLC          X(02)
0020 ALPHANUMERIC  10   FLD          X(20)
0100 ALPHANUMERIC  05   FLD1         X(100)
5000 ALPHANUMERIC  05   FLD2         OCCURS 5 TO 5000
0001 ALPHANUMERIC  10   FILLER       X(01)
0003 ALPHANUMERIC  05   FLD3         X(3)
0004 ALPHANUMERIC  05   FLD4         X(4)
```

If the symbol redefines another variable the `TYPE` is marked with 'R'. If the symbol is an array the `OCCURS` phrase is in the `PICTURE` field.

The last part of the listing file is the summary of warnings and an error in the compilation group:

```
0 warnings in compilation group
2 errors in compilation group
```

### 2.1.7 Debug switches

- `-debug, -d` Enable all run-time error checks.
- `-g` Produce C debugging information in the output.
- `-ftrace` Generate trace code (log executed procedures, if tracing is enabled).
- `-ftraceall` Generate trace code (log executed procedures and statements, if tracing is enabled).
- `-fsource-location` Generate source location code (implied by `-debug` or `-g`).
- `-fstack-check` Enable `PERFORM` stack checking (implied by `-debug` or `-g`).
- `-fdebugging-line` Enable debugging lines (D in indicator column; `>>D` directive).
- `-O` Enable optimization of code size and execution speed. See your C compiler documentation, for example `man gcc` for details.
- `-O2` Optimize even more.

`-Os` Optimize for size. Optimizer will favour code size over execution speed.

`-fnotrunc`  
Do not truncate binary fields according to PICTURE.

### 2.1.8 Miscellaneous

`-ext <extension>`  
Add default file extension.

`-fmfcomment`  
Treat lines with `*` or `/` in column 1 as comment (fixed-form reference-format only).

`-acucomment`  
Treat `|` as an inline comment marker.

`-fsign=ASCII`  
Numeric display sign ASCII (default on ASCII machines).

`-fsign=EBCDIC`  
Numeric display sign EBCDIC (default on EBCDIC machines).

`-fintrinsics=[ALL|intrinsic function name(,name,...)]`  
Allow use of all or specific intrinsic functions without `FUNCTION` keyword.  
Note: defining this within your source with `CONFIGURATION SECTION. REPOSITORY.` is preferred.

`-ffold-copy=LOWER`  
Fold `COPY` subject to lower case (default no transformation).

`-ffold-copy=UPPER`  
Fold `COPY` subject to upper case (default no transformation).

`-save-temps(=<dir>)`  
Save intermediate files (by default, in current directory).

`-fimplicit-init`  
Do automatic initialization of the COBOL runtime system.

## 2.2 Multiple sources

This section describes how to compile a program from multiple source files.

This section also describes how to build a shared library that can be used by any COBOL program and how to use external libraries in COBOL programs.

### 2.2.1 Static linking

The easiest way of combining multiple files is to compile them into a single executable.

One way is to compile all the files in one command:

```
$ cobc -x -o prog main.cob subr1.cob subr2.cob
```

Another way is to compile each file with the option `-c`, and link them at the end. The top-level program must be compiled with the option `-x`.

```
$ cobc -c subr1.cob
$ cobc -c subr2.cob
$ cobc -c -x main.cob
$ cobc -x -o prog main.o subr1.o subr2.o
```

You can link C routines as well using either method:

```
$ cobc -o prog main.cob subrs.c
```

or

```
$ cobc -c subrs.c
$ cobc -c -x main.cob
$ cobc -x -o prog main.o subrs.o
```

Any number of functions can be contained in a single C file.

The linked programs will be called dynamically; that is, the symbol will be resolved at run time. For example, the following COBOL statement

```
CALL "subr" USING X.
```

will be converted into equivalent C code like this:

```
int (*func)() = cob_resolve("subr");
if (func != NULL)
    func (X);
```

With the compiler option `-fstatic-call`, more efficient code will be generated:

```
subr(X);
```

Please notice that this option only takes effect when the called program name is in a literal (like `CALL "subr"`). With a data name (like `CALL SUBR`), the program is still called dynamically.

## 2.2.2 Dynamic linking

There are two methods to achieve this: a driver program, or compiling the main program and subprograms separately.

### 2.2.2.1 Driver program

Compile all programs with the option `-m`:

```
$ cobc -m main.cob subr.cob
```

This creates the shared object files `main.so` and `subr.so`.<sup>4</sup>

Before running the main program, install the module files in your library directory:

```
$ cp subr.so /your/cobol/lib
```

Set the runtime variable `COB_LIBRARY_PATH` to your library directory, and run the main program:

```
$ export COB_LIBRARY_PATH=/your/cobol/lib
```

(*Please notice:* You may set the variable via a runtime configuration file, see Appendix H [Runtime Configuration], page 74. You may also set the variable to directly point to the directory where you compiled the sources.)

Now execute your program:

```
$ cobcrun main
```

### 2.2.2.2 Compiling programs separately

The main program is compiled as usual:

```
$ cobc -x -o main main.cob
```

Subprograms are compiled with the option `-m`:

```
$ cobc -m subr.cob
```

This creates a module file `subr.so`.<sup>5</sup>

Before running the main program, install the module files in your library directory:

```
$ cp subr.so /your/cobol/lib
```

---

<sup>4</sup> The extension used depends on your operating system.

<sup>5</sup> The extension used depends on your operating system.

Now, set the environment variable `COB_LIBRARY_PATH` to your library directory, and run the main program:

```
$ export COB_LIBRARY_PATH=/your/cobol/lib
$ ./main
```

### 2.2.3 Building library

You can build a shared library by combining multiple COBOL programs and even C routines:

```
$ cobc -c subr1.cob
$ cobc -c subr2.cob
$ cc -c subr3.c
$ cc -shared -o libsubrs.so subr1.o subr2.o subr3.o
```

### 2.2.4 Using library

You can use a shared library by linking it with your main program.

Before linking the library, install it in your system library directory:

```
$ cp libsubrs.so /usr/lib
```

or install it somewhere else and set `LD_LIBRARY_PATH`:

```
$ cp libsubrs.so /your/cobol/lib
$ export LD_LIBRARY_PATH=/your/cobol/lib
```

Then, compile the main program, linking the library as follows:

```
$ cobc -x main.cob -L/your/cobol/lib -lsubrs
```

## 2.3 C interface

This chapter describes how to combine C programs with COBOL programs.

### 2.3.1 Writing Main Program in C

Include `libcob.h` in your C program and call `cob_init` before using any COBOL module. Do a cleanup afterwards, either by calling `cob_stop_run` (if your program should terminate) or by calling `cob_tidy` (if your program should execute further on without any more COBOL calls, calling both functions in this sequence can be done multiple times).

```
#include <libcob.h>

int
main (int argc, char **argv)
{
    /* initialize your program */
    ...

    /* initialize the COBOL run-time library */
    cob_init (argc, argv);

    /* rest of your program */
    ...

    /* Clean up and terminate - This does not return */
    cob_stop_run (return_status);
}
```

You can write `cobc_init(0, NULL)`; if you do not want to pass command line arguments to COBOL.

You can compile your C program as follows:

```
cc -c `cob-config --cflags` main.c
```

The compiled object must be linked with libcob as follows:

```
cc -o main main.o `cob-config --libs`
```

### 2.3.2 Static linking with COBOL programs

Let's call the following COBOL module from a C program:

```
----- say.cb -----
IDENTIFICATION DIVISION.
PROGRAM-ID. say.
ENVIRONMENT DIVISION.
DATA DIVISION.
LINKAGE SECTION.
01 hello PIC X(7).
01 world PIC X(6).
PROCEDURE DIVISION USING hello world.
    DISPLAY hello world.
    EXIT PROGRAM.
```

This program accepts two arguments, displays them, and exits.

From the viewpoint of C, this is equivalent to a function having the following prototype:

```
extern int say(char *hello, char *world);
```

So, your main program will look like as follows:

```
----- hello.c -----
#include <libcob.h>

extern int say(char *hello, char *world);

int
main()
{
    int ret;
    char hello[8] = "Hello, ";
    char world[7] = "world!";

    /* initialize the COBOL run-time library */
    cob_init(0, NULL);

    /* call the static module and store its return code */
    ret = say(hello, world);

    /* shutdown the COBOL run-time library, keep program running */
    (void)cob_tidy();

    return ret;
}
```

Compile these programs as follows:

```
$ cc -c `cob-config --cflags` hello.c
```

```

$ cobc -c -static say.cob
$ cobc -x -o hello hello.o say.o
$ ./hello
Hello, world!

```

### 2.3.3 Dynamic linking with COBOL programs

You can find a COBOL module having a specific name by using the C function `cob_resolve`, which takes the module name as a string and returns a pointer to the module function.

`cob_resolve` returns NULL if there is no module. In this case, the function `cob_resolve_error` returns the error message.

Let's see an example:

```

---- hello-dynamic.c -----
#include <libcob.h>

static int (*say)(char *hello, char *world);

int main()
{
    int ret;
    char hello[8] = "Hello, ";
    char world[7] = "world!";

    /* initialize the COBOL run-time library */
    cob_init(0, NULL);

    /* Find the module with PROGRAM-ID "say". */
    say = cob_resolve("say");

    /* If there is no such module, show error and exit. */
    if(say == NULL) {
        fprintf(stderr, "%s\n", cob_resolve_error());
        exit(1);
    }

    /* Call the module found ... */
    ret = say(hello, world);

    /* ...and exit with the return code. */
    cob_stop_run(ret);
}
-----

```

Compile these programs as follows:

```

$ cc -c 'cob-config --cflags' hello-dynamic.c
$ cobc -x -o hello hello-dynamic.o
$ cobc -m say.cob
$ export COB_LIBRARY_PATH=.
$ ./hello
Hello, world!

```

### 2.3.4 Static linking with C programs

Let's call the following C function from COBOL:

```

---- say.c -----
int say(char *hello, char *world)
{
    int i;
    for(i = 0; i < 7; i++)
        putchar(hello[i]);
    for(i = 0; i < 6; i++)
        putchar(world[i]);
    putchar('\n');
    return 0;
}
-----

```

This program is equivalent to the program in `say.cob` above.

Note that, unlike C, the arguments passed from COBOL programs are not terminated by the null character (i.e., `'\0'`).

You can call this function in the same way you call COBOL programs:

```

---- hello.cob -----
IDENTIFICATION DIVISION.
PROGRAM-ID. hello.
ENVIRONMENT DIVISION.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 hello PIC X(7) VALUE "Hello, ".
01 world PIC X(6) VALUE "world!".
PROCEDURE DIVISION.
CALL "say" USING hello world.
STOP RUN.
-----

```

Compile these programs as follows:

```

$ cc -c say.c
$ cobc -c -static -x hello.cob
$ cobc -x -o hello hello.o say.o
$ ./hello
Hello, world!

```

### 2.3.5 Dynamic linking with C programs

You can create a dynamically-linked module from a C program by passing an option `-shared` to the C compiler:

```

$ cc -shared -o say.so say.c
$ cobc -x hello.cob
$ export COB_LIBRARY_PATH=.
$ ./hello
Hello, world!

```

### 2.3.6 Redirecting output to a (FILE \*)

From a module written in C you can call `cob_set_runtime_option` to set the exact (FILE \*) which is used to write trace data to. In `common.h` is the following:

```

enum cob_runtime_option_switch {
    COB_SET_RUNTIME_TRACE_FILE          /* 'p' is FILE * */
    COB_SET_RUNTIME_DISPLAY_PRINTER_FILE /* 'p' is FILE * */
}

```

```
    COB_SET_RUNTIME_RESCAN_ENV          /* rescan environment variables */  
    COB_SET_RUNTIME_DISPLAY_PUNCH_FILE /* 'p' is FILE * */  
};  
COB_EXPIMP void cob_set_runtime_option (enum cob_runtime_option_switch opt, void *p);
```

So from you C code you can tell the GnuCOBOL runtime to redirect TRACE output by:

```
cob_set_runtime_option (COB_SET_RUNTIME_TRACE_FILE,  
                       (void*)((FILE*)myfd));
```

You could also redirect all DISPLAY UPON PRINTER output to a file by:

```
cob_set_runtime_option (COB_SET_RUNTIME_DISPLAY_PRINTER_FILE,  
                       (void*)((FILE*)myfd));
```

You could also redirect all DISPLAY UPON SYSPUNCH output to a file by:

```
cob_set_runtime_option (COB_SET_RUNTIME_DISPLAY_PUNCH_FILE,  
                       (void*)((FILE*)myfd));
```

Another routine can be used to return the current value of the option.

```
COB_EXPIMP void *  
cob_get_runtime_option (enum cob_runtime_option_switch opt);
```

## 3 Customize

### 3.1 Customizing compiler

These settings are effective at compile-time.

Environment variables (default value in brackets):

**COB\_CC** C compiler ("gcc")

**COB\_CFLAGS**  
Flags passed to the C compiler ("-I\$(PREFIX)/include")

**COB\_LDFLAGS**  
Flags passed to the C compiler ("")

**COB\_LIBS** Standard libraries linked with the program ("-L\$(PREFIX)/lib -lcob")

**COB\_LDADD**  
Additional libraries linked with the program ("")

### 3.2 Customizing library

These settings are effective at run-time. You can set them either via the environment or by a runtime configuration file.

To set the global runtime configuration file export **COB\_RUNTIME\_CONFIG** to point to your configuration file. To set an explicit runtime configuration file for a single run via **cobcrun** you can use its option **-c file**, **--config=file**.

For displaying the current runtime settings you can use the option **-r**, **--runtime-env** of **cobcrun**.

For a complete list of runtime variables, aliases, their default values and options to set them see Appendix H [Runtime Configuration], page 74.

## 4 Optimize

### 4.1 Optimize options

There are five compiler options for optimization: `-O0`, `-O`, `-Os`, `-O2`, `-O3`. These options enable optimization at both translation (from COBOL to C) and compilation (C to assembly) levels.

Currently, there is no difference between these optimization options at the translation level.

The option `-O`, `-Os` or `-O2` is passed to the C compiler as is and used for C level optimization.

### 4.2 Optimize call

When a `CALL` statement is executed, the called program is linked at run time. By specifying the compiler option `-fstatic-call`, you can statically link the program at compile time and call it efficiently. (see Section 2.2.1 [Static linking], page 9)

### 4.3 Optimize binary

By default, data items of usage `binary` or `comp` are stored in big-endian form. On those machines whose native byte order is little-endian, this is not quite efficient.

If you prefer, you can store binary items in the native form of your machine. Set the config option `binary-byteorder` to `native` in your config file (see Chapter 3 [Customize], page 16).

In addition, setting the option `binary-size` to `2-4-8` or `1-2-4-8` is more efficient than others.

## 5 Debug

### 5.1 Debug options

The compiler option `-debug` can be used during the development of your programs. It enables all run-time error checking, such as subscript boundary checks and numeric data checks, and displays run-time errors with source locations.

## 6 Non-standard extensions

### 6.1 SELECT ASSIGN TO

A file may be assigned to a literal file, a file in a variable, or a file in an environment variable.

#### 6.1.1 Literal file.

Assign to a literal file.

Select *file* assign to `"/tmp/myfile.txt"`.

#### 6.1.2 <variable>

Assign to a file which name is read from a variable.

Select *file* assign to `my-file`.

```
01 my-file          pic x(512).
```

Move `"/tmp/myfile.txt"` to `my-file`.

Open output `<file>`.

#### 6.1.3 <environment variable>

Assign to a file in an environment variable.

```
export myfile=/tmp/myfile.txt
```

Select *file* assign to external `myfile`.

## 6.2 Indexed file packages

<This section is in progress.>

### 6.3 Extended ACCEPT statement

Extended ACCEPT statements allow for full control of items accepted from the screen. Items accept by line and column positioning.

All commands following WITH are optional.

```
ACCEPT variable-1
```

```
  LINE variable-2 | literal-1 COLUMN variable-3 | literal-2
```

```
  WITH
```

```
    AUTO-SKIP | AUTO
```

```
    BACKGROUND-COLOR variable-4 | literal-3
```

```
    BELL | BEEP
```

```
    BLINK
```

```
    FOREGROUND-COLOR variable-5 | literal-4
```

```
    LOWLIGHT | HIGHLIGHT
```

```
    PROMPT
```

```
    PROTECTED
```

```
    SIZE [IS] variable-6 | literal-5
```

```
    UPDATE
```

```
  ON EXCEPTION
```

```
    exception processing
```

```
  NOT ON EXCEPTION
```

```
    normal processing
```

```
END-ACCEPT.
```

### 6.3.1 LINE

The line number of *variable-2* or *literal-1* to accept the field.

### 6.3.2 COLUMN

The column number of *variable-3* or *literal-2* to accept the field.

### 6.3.3 AUTO-SKIP

The word `AUTO` may be used for `AUTO-SKIP`.

With this option the `ACCEPT` statement returns after the last character is typed at the end of the field. This is the same as if the Enter key were pressed.

Without this option the cursor remains at the end of the field and waits for the user to press Enter.

The Right-Arrow key returns from the end of the field. The Left-Arrow key returns from the beginning. See Section 6.4 [`ACCEPT` special], page 21.

The Alt-Right-Arrow and Alt-Left-Arrow keys never `AUTO-SKIP`.

### 6.3.4 BACKGROUND-COLOR

The background color is the color used behind the characters.

*Variable-4* or *literal-3* must be numeric. See file `screenio.cpy` for the color assignments to *variable-4* or *literal-3*.

### 6.3.5 BELL

The word `BEEP` may be used for `BELL`.

The system beeps when the cursor moves to accept from this field. On some systems, there is no sound. Some other method may indicate a beep, such a flashing screen or pop up window.

### 6.3.6 BLINK

The field blinks while the user enters the data. This can help small menu selection fields to stand out.

### 6.3.7 FOREGROUND-COLOR

The foreground color is the color used for the characters.

*Variable-5* or *literal-4* must be numeric. See file `screenio.cpy` for the color assignments to *variable-5* or *literal-4*.

### 6.3.8 LOWLIGHT

The `LOWLIGHT` and `HIGHLIGHT` phrases vary the intensity of the field.

`LOWLIGHT` displays with lower intensity and `HIGHLIGHT` displays with higher intensity. Having neither `LOWLIGHT` nor `HIGHLIGHT` displays at normal intensity.

These may have different levels of intensity, if at all, depending on the make and model of the screens.

### 6.3.9 PROMPT

Display the field with prompt characters as the cursor moves to accept from this field.

### 6.3.10 PROTECTED

`PROTECTED` is ignored.

### 6.3.11 SIZE

The size of *variable-1* to accept from the screen.

*Variable-6* or *literal-5* must be numeric.

SIZE <greater than zero>

If *variable-6* or *literal-5* is less than the length of *variable-1* then only the SIZE number of characters accept into the field. *Variable-1* pads with spaces after SIZE to the end of the field.

If *variable-6* or *literal-5* is greater than *variable-1*, then the screen pads with spaces after *variable-1* to the SIZE length.

SIZE ZERO

<SIZE option not specified>

The *variable-1* accepts to its field length.

### 6.3.12 UPDATE

The contents of *variable-1* displays on the screen as the ACCEPT begins. This allows the user to update the field without having to type it all again.

Without this option, the ACCEPT field is always blank.

### 6.3.13 ON EXCEPTION

Check the special register `cob-crt-status` for the special key that was pressed. This includes Escape, Tab, Back-Tab, F-keys, arrows, etc... See `screenio.cpy` for the values.

### 6.3.14 NOT ON EXCEPTION

Reset any F-key indicator because no special key was pressed.

## 6.4 ACCEPT special keys

Special keys are available for extended ACCEPT statements.

The `COB-CRT-STATUS` values are in the `screenio.cpy` copy file.

### 6.4.1 Arrow keys

The Left-Arrow key moves the cursor to the left. Without `AUTO-SKIP` the cursor stops at the beginning of the field. With `AUTO-SKIP` it returns with the `COB-SCR-KEY-LEFT` value of 2009. See Section 6.3 [Extended ACCEPT], page 19.

The Alt-Left-Arrow key is the same as Left-Arrow except that it never returns, even for `AUTO-SKIP`.

The Right-Arrow key moves the cursor to the right. Without `AUTO-SKIP` the cursor stops at the end of the field. With `AUTO-SKIP` it returns with the `COB-SCR-KEY-RIGHT` value of 2010. See Section 6.3 [Extended ACCEPT], page 19.

The Alt-Right-Arrow key is the same as Right-Arrow except that it never returns, even for `AUTO-SKIP`.

### 6.4.2 Backspace key

The Backspace key moves the cursor, and the remainder of the text, to the left.

### 6.4.3 Delete keys

The Delete key deletes the cursor's character and moves the remainder of the text to the left. The cursor does not move.

The Alt-Delete key deletes all text from the cursor to the end of the field.

### 6.4.4 End key

The End key moves the cursor after the last non-space character. Pressing the End key again moves the cursor to the end of the field. Repeated pressing moves the cursor back and forth.

### 6.4.5 Home key

The Home key moves the cursor to the first non-space character. Pressing the Home key again moves the cursor to the beginning of the field. Repeated pressing moves the cursor back and forth.

### 6.4.6 Insert key

The Insert key changes the insert mode.

The value of the insert mode is used in all following ACCEPT statements while the program is running.

When the insert mode is on, typed characters move the existing characters to the right until field is full. When it is off, typed characters type over existing characters.

Note: The insert mode is ignored for fields with a size of 1.

The insert mode can also be changed by the COB\_INSERT\_MODE setting at any time, see Appendix H [Runtime Configuration], page 74.

### 6.4.7 Tab keys

The Tab key returns from the ACCEPT with the COB-SCR-TAB value of 2007.

The Shift-Tab key returns with the COB-SCR-BACK-TAB value of 2008.

## 6.5 Extended DISPLAY statement

Extended DISPLAY statements allow for full control of items that display on the screen. Items display by line and column positioning.

```
DISPLAY variable-1 | literal-1 | figurative constant
  LINE line COLUMN column
  WITH BELL
    BLANK LINE | SCREEN
    ERASE EOL | EOS
    SIZE [IS] variable-2 | literal-2
END-DISPLAY.
```

### 6.5.1 BELL

Ring the bell. It is optional.

### 6.5.2 BLANK

Clear the whole line or screen. It is optional.

BLANK LINE

Clear the line from the beginning of the line to the end of the line.

BLANK SCREEN

Clear the whole screen.

### 6.5.3 ERASE

Clear the line or screen from `LINE` and `COLUMN`. It is optional.

`ERASE EOL`

Clear the line from `LINE` and `COLUMN` to the end of the line.

`ERASE EOS`

Clear the screen from `LINE` and `COLUMN` to the end of the screen.

### 6.5.4 SIZE

The size of *variable-1*, *literal-1*, or *figurative-constant* to display onto the screen. It is optional.

`SIZE positive-integer`

If `SIZE` is less than the length of *variable-1* or *literal-1* then only the `SIZE` number of characters display.

If `SIZE` is greater than the length of *variable-1* or *literal-1*, then the screen pads with spaces after the field to the `SIZE` length.

Figurative constants display repeatedly the number of times in `SIZE`. Except that `LOW-VALUES` always positions the cursor (see `SIZE ZERO` below).

`SIZE ZERO`

<`SIZE option not specified`>

*Variable-1* or *literal-1* displays with the field length.

### 6.5.5 Figurative Constants

Certain figurative constants and values have special functions. All other figurative constants display as a single character.

`SPACE` Display spaces from `LINE` and `COLUMN` to the end of the screen. This is the same as `WITH ERASE EOS`.

`LOW-VALUE`

Position the cursor to `LINE` and `COLUMN`. The next `DISPLAY` statement does not need a `LINE` or `COLUMN` to display at that position.

`ALL X"01"`

Display spaces from `LINE` and `COLUMN` to the end of the line. This is the same as `WITH ERASE EOL`.

`ALL X"02"`

Clear the whole screen. This is the same as `WITH BLANK SCREEN`.

`ALL X"07"`

Ring the bell. This is the same as `WITH BELL`.

## 6.6 CONTENT-LENGTH

FUNCTION `CONTENT-LENGTH` returns the length of `NUL` byte terminated data given a pointer:

```

identification division.
program-id. zlen.
data division.
working-storage section.
01 ptr    usage pointer.
01 str    pic x(4) value z"abc".

```

\*> Testing `CONTENT-LENGTH`

```
procedure division.  
  
set ptr to address of str  
display content-length(ptr)  
  
goback.  
end program hosted.
```

## 6.7 CONTENT-OF

FUNCTION CONTENT-OF returns an alphanumeric field given a pointer and optional length:

Data from pointer is returned as a COBOL field either by scanning for a NUL byte or using the optional length. Reference modification of result allowed.

```
identification division.  
program-id. contents.  
data division.  
working-storage section.  
01 ptr    usage pointer.  
01 str    pic x(4) value z"abc".
```

\*> Testing CONTENT-OF

```
procedure division.  
  
set ptr to address of str  
display content-of(ptr)  
display content-of(ptr, 2)  
display content-of(ptr)(2:2)  
  
goback.  
end program hosted.
```

## 7 System Routines

For a complete list of supported system routines, see Appendix D [System routines], page 64.

### 7.1 CBL\_GC\_GETOPT

CBL\_GC\_GETOPT provides the quite well-known option parser, getopt, for GnuCOBOL. The usage of this system routine is described by the following example.

```

identification division.
program-id. prog.

data division.
working-storage section.
    78 shortoptions value "jkl".

    01 longoptions.
        05 optionrecord occurs 2 times.
            10 optionname    pic x(25).
            10 has-value     pic 9.
            10 valpoint     pointer value NULL.
            10 return-value  pic x(4).

    01 longind    pic 99.
    01 long-only  pic 9 value 1.

    01 return-char pic x(4).
    01 opt-val     pic x(10).

    01 counter    pic 9 value 0.

```

We first need to define the necessary fields for getopt's shortoptions (so), longoptions (lo), longoption index (longind), long-only-option (long-only) and also the fields for return values return-char and opt-val (arbitrary size with trimming, see return codes).

The shortoptions are written down as an alphanumeric field (i.e., a string with arbitrary size) as follows:

```
"ab:c::d"
```

This means we want getopt to look for shortoptions named a, b, c or d and we demand an option value for b and we are accepting an optional one for c.

The longoptions are defined as a table of records with oname, has-value, valpoint and val.

- oname defines the name of a longoption.
- has-value defines if an option value is demanded (has-val = 1), optional (has-val = 2) or not required (has-val = 0).
- valpoint is a pointer used to specify an address to save getopt's return value to. The pointer is optional. If it is NULL, getopt returns a value as usual. If you use the pointer it has to point to a PIC X(4) field.
- The field val is a PIC X(4) character which is returned if the longoption was recognized.

The longoption structure is immutable! You can only vary the number of records.

Now we have the tools to run CBL\_GC\_GETOPT within the procedure division.

```

procedure division.
    move "version" to optionname (1).

```

```

move 0          to has-value   (1).
move "v"        to return-value (1).

move "verbose" to optionname   (2).
move 0          to has-value   (2).
move "V"        to return-value (2).

perform with test after until return-code = -1
  call 'CBL_GC_GETOPT' using
    by reference shortoptions longoptions longind
    by value long-only
    by reference return-char opt-val
  end-call

  display return-char end-display
  display opt-val     end-display
end-perform
stop run.

```

The example shows how we initialize all parameters and call the routine until `CBL_GC_GETOPT` runs out of options and returns -1.

If the option is recognized, `return-char` contains the option character. Otherwise, `return-char` will contain one of the following:

```

?          undefined or ambiguous option
1          non-option (only if first byte of so is '-')
0          valpoint != NULL and we are writing the return value to the specified address
-1         no more options (or reached the first non-option if first byte of so is '+')

```

The return-code of `CBL_GC_GETOPT` is one of:

```

1          a non-option (only if first byte of so is '-')
0          valpoint != NULL and we are writing the return value to the specified address
-1         no more options (or reach the first non-option if first byte of so is '+')
2          truncated option value in opt-val (because opt-val was too small)
3          regular answer from getopt

```

## 7.2 CBL\_GC\_HOSTED

`CBL_GC_HOSTED` provides access to the following C hosted variables:

- `argc` to binary-long by value
- `argv` to pointer to char \*\*
- `stdin`, `stdout`, `stderr` to pointer
- `errno` giving address of errno in pointer to binary-long, use based for more direct access

and conditional access to the following variables:

- `tzname` pointer to pointer to array of two char pointers
- `timezone` C long, will be seconds west of UTC
- `daylight` C int, will be 1 during daylight savings

System will need to `HAVE_TIMEZONE` defined for these to return anything meaningful. Attempts made when they are not available return 1 from `CBL_GC_HOSTED`.

It returns 0 when match, 1 on failure, case matters as does length, `arg` won't match.

The usage of this system routine is described by the following example.

```
HOSTED identification division.
  program-id. hosted.
  data division.
  working-storage section.
  01 argc  usage binary-long.
  01 argv  usage pointer.

  01 stdin usage pointer.
  01 stdout usage pointer.
  01 stderr usage pointer.

  01 errno usage pointer.
  01 err   usage binary-long based.

  01 domain usage float-long value 3.0.

  01 tzname usage pointer.
  01 tznames usage pointer based.
     05 tzs usage pointer occurs 2 times.

  01 timezone  usage binary-long.
  01 daylight  usage binary-short.

*> Testing CBL_GC_HOSTED
  procedure division.
  call "CBL_GC_HOSTED" using stdin "stdin"
  display "stdin          : " stdin
  call "feof" using by value stdin
  display "feof stdin    : " return-code

  call "CBL_GC_HOSTED" using stdout "stdout"
  display "stdout        : " stdout
  call "fprintf" using by value stdout by content "Hello" & x"0a"

  call "CBL_GC_HOSTED" using stderr "stderr"
  display "stderr        : " stderr
  call "fprintf" using by value stderr by content "on err" & x"0a"

  call "CBL_GC_HOSTED" using argc "argc"
  display "argc          : " argc

  call "CBL_GC_HOSTED" using argv "argv"
  display "argv          : " argv

  call "args" using by value argc argv
```

```

call "CBL_GC_HOSTED" using errno "errno"
display "&errno          : " errno
set address of err to errno
display "errno          : " err
call "acos" using by value domain
display "errno after acos(3.0): " err ", EDOM is 33"

call "CBL_GC_HOSTED" using argc "arg"
display "'arg' lookup      : " return-code
call "CBL_GC_HOSTED" using null "argc"
display "null with argc   : " return-code
display "argc is still    : " argc

*> the following only returns zero if the system has HAVE_TIMEZONE set

call "CBL_GC_HOSTED" using daylight "daylight "
display "'timezone' lookup  : " return-code

if return-code not = 0
  display "system doesn't has timezone"
else

  display "timezone is      : " timezone

  call "CBL_GC_HOSTED" using daylight "daylight "
  display "'daylight' lookup  : " return-code
  display "daylight is      : " daylight

  set environment "TZ" to "PST8PDT"
  call static "tzset" returning omitted on exception continue end-call

  call "CBL_GC_HOSTED" using tzname "tzname"
  display "'tzname' lookup    : " return-code

  *> tzs(1) will point to z"PST" and tzs(2) to z"PDT"
  if return-code equal 0 and tzname not equal null then
    set address of tznames to tzname
    if tzs(1) not equal null then
      display "tzs #1          : " tzs(1)
    end-if
    if tzs(2) not equal null then
      display "tzs #2          : " tzs(2)
    end-if
  end-if

end-if

goback.
end program hosted.

```

### 7.3 CBL\_GC\_NANOSLEEP

CBL\_GC\_NANOSLEEP allows you to pause the program for nanoseconds. The actual precision depends on the system.

```
*> Waiting a half second
  call "CBL_GC_NANOSLEEP" using "500000000" end-call

*> Waiting five seconds using compiler string catenation for readability
  call "CBL_GC_NANOSLEEP" using "500" & "0000000" end-call
```

### 7.4 CBL\_GC\_FORK

CBL\_GC\_FORK allows you to fork the current COBOL process to a new one. The current content of the process' storage (including LOCAL-STORAGE) will be identical, any file handles get invalid in the new process, positions and file / record locks are only available to the original process.

This system routine is not available on Windows (exception: GCC on Cygwin).

Parameters

none

Returns PID (the child process gets '0' returned, the calling process gets the PID of the created children). Negative values are returned for system dependent error codes and -1 if the function is not available on the current system.

```
IDENTIFICATION DIVISION.
PROGRAM-ID. prog.
DATA DIVISION.
WORKING-STORAGE SECTION.
01 CHILD-PID PIC S9(9) BINARY.
01 WAIT-STS PIC S9(9) BINARY.
PROCEDURE DIVISION.

CALL "CBL_GC_FORK" RETURNING CHILD-PID END-CALL
EVALUATE TRUE
  WHEN CHILD-PID = ZERO
    PERFORM CHILD-CODE
  WHEN CHILD-PID > ZERO
    PERFORM PARENT-CODE
  WHEN CHILD-PID = -1
    DISPLAY 'CBL_GC_FORK is not available '
      'on the current system!'
    END-DISPLAY
    PERFORM CHILD-CODE
    MOVE 0 TO CHILD-PID
    PERFORM PARENT-CODE
  WHEN OTHER
    MULTIPLY CHILD-PID BY -1 END-MULTIPLY
    DISPLAY 'CBL_GC_FORK returned system error: '
      CHILD-PID
    END-DISPLAY
END-EVALUATE

STOP RUN.
```

```

CHILD-CODE.
  CALL "$SLEEP" USING 1 END-CALL
  DISPLAY "Hello, I am the child"
  END-DISPLAY
  MOVE 2 TO RETURN-CODE

CONTINUE.

PARENT-CODE.
  DISPLAY "Hello, I am the parent"
  END-DISPLAY
  CALL "CBL_GC_WAITPID" USING CHILD-PID RETURNING WAIT-STS
  END-CALL
  MOVE 0 TO RETURN-CODE
  EVALUATE TRUE
    WHEN WAIT-STS >= 0
      DISPLAY 'Child ended with status: '
        WAIT-STS
      END-DISPLAY
    WHEN WAIT-STS = -1
      DISPLAY 'CBL_GC_WAITPID is not available '
        'on the current system!'
      END-DISPLAY
    WHEN WAIT-STS < -1
      MULTIPLY -1 BY WAIT-STS END-MULTIPLY
      DISPLAY 'CBL_GC_WAITPID returned system error: ' WAIT-STS
      END-DISPLAY
  END-EVALUATE

CONTINUE.

```

## 7.5 CBL\_GC\_WAITPID

CBL\_GC\_WAITPID allows you to wait until another system process ended. Additionally you can check the process' return code.

Parameters: none Returns: function-status / child-status Negative values are returned for system dependent error codes and -1 if the function is not available on the current system.

```

CALL "CBL_GC_WAITPID" USING CHILD-PID RETURNING WAIT-STS
END-CALL
MOVE 0 TO RETURN-CODE
DISPLAY 'CBL_GC_WAITPID ended with status: ' WAIT-STS
END-DISPLAY

```

## Appendix A Compiler cobc options

The following list of options was extracted from `cobc --help` and shows all available compiler options with a short description.

### A.1 Common Options

- `-h, -help` display this help and exit
- `-V, -version`  
display compiler version and exit
- `-i, -info` display compiler information (build/environment) and exit
- `-v, -verbose`  
verbose mode, display additional information; multiple `-v` options increase the verbosity, the maximum is 3 as follows: (1) display compiler version and the commands invoked by the compiler, (2) pass verbose option to assembler/compiler (3) pass verbose option to linker
- `-q, -brief`  
reduced displays, commands invoked not shown
- `-###` like `-v` but commands not executed
- `-x` build an executable program
- `-m` build a dynamically loadable module (default)
- `-j [args], -job[=args]`  
run program after build, passing *args*
- `-std=diect`  
warnings/features for a specific dialect *dialect* can be one of: default, cobol2014, cobol2002, cobol85, xopen, ibm-strict, ibm, mvs-strict, mvs, mf-strict, mf, bs2000-strict, bs2000, acu-strict, acu, rm-strict, rm; see configuration files in directory `config`
- `-F, -free` use free source format
- `-fixed` use fixed source format (default)
- `-O, -O2, -O3, -Os`  
enable optimization
- `-O0` disable optimization
- `-g` enable C compiler debug and stack check
- `-d, -debug`  
enable all run-time error checking, equal to `-fstack-check -fec=EC-ALL`
- `-fec=exception-name`  
enable code generation for *exception-name*, sets `-fsource-location`
- `-fno-ec=exception-name`  
disable code generation for *exception-name*
- `-o file` place the output into *file*
- `-b` combine all input files into a single dynamically loadable module
- `-E` preprocess only; do not compile or link

- `-C` translation only; convert COBOL to C
- `-S` compile only; output assembly file
- `-c` compile and assemble, but do not link
- `-T file` generate and place a wide program listing into *file*
- `-t file` generate and place a program listing into *file*
- `--tlines=lines`  
specify lines per page in listing, default = 55
- `-P[=dir or file]`  
generate preprocessed program listing (.lst)
- `-Xref` generate cross reference through 'cobxref' (V. Coen's 'cobxref' must be in path)
- `-I directory`  
add *directory* to copy/include search path
- `-L directory`  
add *directory* to library search path
- `-l lib` link the library *lib*
- `-A options`  
add *options* to the C compile phase
- `-Q options`  
add *options* to the C link phase
- `-D define` define *define* for COBOL compilation
- `-K entry` generate CALL to *entry* as static
- `-conf=file`  
user-defined dialect configuration; see -std
- `-list-reserved`  
display reserved words
- `-list-intrinsics`  
display intrinsic functions
- `-list-mnemonics`  
display mnemonic names
- `-list-system`  
display system routines
- `-save-temps[=dir]`  
save intermediate files; default: current directory
- `-ext extension`  
add file extension for resolving COPY

## A.2 Warning options

- `-Wall` enable most warnings (all except as noted below)
- `-Wextra` like -Wall but enable some extra warning flags
- `-w` disable all warnings

- Wno-warning  
disable warning enabled by default, -Wall or -Wextra
- Wadditional  
additional warnings only raised with -Wall
- Wno-unfinished  
do not warn if unfinished features are used; *always* active
- Wno-pending  
do not warn if pending features are mentioned; *always* active
- Wno-ignored-error  
do not warn about errors in unreachable code parts and so normally ignored; *always* active
- Wobsolete  
warn if obsolete features are used
- Warchaic  
warn if archaic features are used
- Wredefinition  
warn about non-referenced ambiguous data items
- Wtruncate  
warn about field truncation from constant assignments
- Wpossible-truncate  
warn about possible field truncation; *not* set with -Wall
- Woverlap  
warn about overlapping MOVE of items
- Wpossible-overlap  
warn about MOVE of items that may overlap depending on variables; *not* set with -Wall
- Wparentheses  
warn about lack of parentheses around AND within OR
- Wstrict-typing  
warn strictly about type mismatch
- Wno-implicit-define  
do not warn about implicitly defined data items; *always* active
- Wno-corresponding  
do not warn about CORRESPONDING with no matching items; *always* active
- Winitial-value  
warn if initial VALUE clause is ignored
- Wprototypes  
warn about missing FUNCTION prototypes/definitions
- Warithmic-osvs  
warn if arithmetic expression precision has changed
- Wcall-params  
warn about non 01/77 items for CALL parameters; *not* set with -Wall
- Wconstant-expression  
warn about expressions that always resolve to true/false

- `-Wcolumn-overflow`  
warn about text after program-text area, FIXED format; *not* set with `-Wall`
- `-Wterminator`  
warn about lack of scope terminator END-XXX; *not* set with `-Wall`
- `-Wlinkage`  
warn about dangling LINKAGE items; *not* set with `-Wall`
- `-Wunreachable`  
warn about likely unreachable statements; *not* set with `-Wall`
- `-Wno-dialect`  
do not warn about dialect specific issues; *always* active
- `-Wdangling-text`  
warn source text after program-area; *not* set with `-Wall`
- `-Wno-others`  
do not warn about different issues; *always* active
- `-Werror` treat all warnings as errors
- `-Wno-error`  
don't treat warnings as errors
- `-Werror=warning`  
treat specified *warning* as error
- `-Wno-error=warning`  
don't treat specified *warning* as error

### A.3 Compiler options

- `-fsign=[ASCII|EBCDIC]`  
define display sign representation; default: machine native
- `-ffold-copy=[UPPER|LOWER]`  
fold COPY subject to value; default: no transformation
- `-ffold-call=[UPPER|LOWER]`  
fold PROGRAM-ID, CALL, CANCEL subject to value; default: no transformation
- `-fdefaultbyte=value`  
initialize fields without VALUE to value; decimal 0..255 or any quoted character;  
default: initialize to picture
- `-fmax-errors=number`  
maximum number of errors to report before compilation is aborted; default: 128
- `-fintrinsics=[ALL|intrinsic function name(,name,...)]`  
intrinsics to be used without FUNCTION keyword
- `-fdump=scope`  
dump data fields on abort, *scope* may be a combination of: ALL, WS, LS, RD, FD, SC,  
LO
- `-fcallfh=name`  
specifies *name* to be used for I/O as external provided EXTFH interface module
- `-fno-remove-unreachable`  
disable remove of unreachable code; turned off by `-g`

- ftrace** generate trace code; scope: executed SECTION/PARAGRAPH
- ftraceall**  
generate trace code; scope: executed SECTION/PARAGRAPH/STATEMENTS
- fsyntax-only**  
syntax error checking only; don't emit any output
- fdebugging-line**  
enable debugging lines; 'D' in indicator column or floating >>D
- fsource-location**  
generate source location code; turned on by `-debug/-g/-ftraceall/-fec`
- fimplicit-init**  
automatic initialization of the COBOL runtime system
- fno-recursive-check**  
disable check of recursive program call; effectively compiling as RECURSIVE program
- fstack-check**  
PERFORM stack checking; turned on by `-debug` or `-g`
- fwrite-after**  
use AFTER 1 for WRITE of LINE SEQUENTIAL; default: BEFORE 1
- fmfcomment**  
'\*' or '/' in column 1 treated as comment; FIXED format only
- facucomment**  
'\$' in indicator area treated as '\*', '|' treated as floating comment
- fnotrunc**  
allow numeric field overflow; non-ANSI behaviour
- fodoslide**  
adjust items following OCCURS DEPENDING; implies `-fcomplex-odo`
- fsingle-quote**  
use a single quote (apostrophe) for QUOTE; default: double quote
- foptional-file**  
treat all files as OPTIONAL; unless NOT OPTIONAL specified
- fstatic-call**  
output static function calls for the CALL statement
- fno-gen-c-decl-static-call**  
disable generation of C function declarations for subroutines with static CALL
- fgen-c-line-directives**  
generate source location directives in C code; useful for source-level debugging
- fgen-c-labels**  
generate extra labels in C sources; useful for source-level debugging
- fno-headers**  
suppress all headers and output of compilation options from listing while keeping page breaks
- fno-tsource**  
suppress source from listing

- `-fno-tmessages`  
suppress warning and error summary from listing
- `-ftsymbols`  
specify symbols in listing
- `-fno-diagnostics-show-option`  
suppress output of option that directly controls the diagnostic

## A.4 Compiler dialect configuration options

- `-freserved-words=value`  
use of complete/fixed reserved words
- `-ftab-width=1..12`  
set number of spaces that are assumed for tabs
- `-ftext-column=72..255`  
set right margin for source (fixed format only)
- `-fpic-length=number`  
maximum number of characters allowed in the PICTURE character-string
- `-fword-length=1..63`  
maximum word-length for COBOL (= programmer defined) words
- `-fliteral-length=number`  
maximum literal size in general
- `-fnumeric-literal-length=1..38`  
maximum numeric literal size
- `-fbinary-size=value`  
binary byte size - defines the allocated bytes according to PIC, may be one of: 2-4-8, 1-2-4-8, 1-8
- `-fbinary-byteorder=value`  
binary byte order, may be one of: native, big-endian
- `-fassign-clause=value`  
how to interpret `ASSIGN word:` as `ASSIGN EXTERNAL word` or `ASSIGN DYNAMIC word`, may be one of: `dynamic`, `external`, `ibm` (= external), `mf` (= dynamic)
- `-fscreen-section-rules=value`  
which compiler's rules to apply to `SCREEN SECTION` item clauses, may be one of: `acu`, `gc`, `mf`, `rm`, `std`, `xopen`
- `-fdpc-in-data=value`  
whether `DECIMAL-POINT IS COMMA` has effect in `XML/JSON GENERATE`, may be one of: `none`, `xml`, `json`, `all`
- `-ffilename-mapping`  
resolve file names at run time using environment variables
- `-fpretty-display`  
alternate formatting of numeric fields
- `-fbinary-truncate`  
numeric truncation according to ANSI
- `-fcomplex-odo`  
allow complex `OCCURS DEPENDING ON`

- `-findirect-redefines`  
allow REDEFINES to other than last equal level number
- `-flarger-redefines-ok`  
allow larger REDEFINES items
- `-frelax-syntax-checks`  
allow certain syntax variations (e.g. REDEFINES position)
- `-fref-mod-zero-length`  
allow zero length reference-modification (only changed with EC-BOUND-REF-MOD active)
- `-frelax-level-hierarchy`  
allow non-matching level numbers
- `-fselect-working`  
require ASSIGN USING items to be in WORKING-STORAGE
- `-flocal-implies-recursive`  
LOCAL-STORAGE SECTION implies RECURSIVE attribute
- `-fsticky-linkage`  
LINKAGE SECTION items remain allocated between invocations
- `-fmove-ibm`  
MOVE operates as on IBM (left to right, byte by byte)
- `-fperform-osvs`  
exit point of any currently executing perform is recognized if reached
- `-farithmetic-osvs`  
limit precision in intermediate results to precision of final result (less accurate)
- `-fconstant-folding`  
evaluate constant expressions at compile time
- `-fhostsign`  
allow hexadecimal value 'F' for NUMERIC test of signed PACKED DECIMAL field
- `-fprogram-name-redefinition`  
program names don't lead to a reserved identifier
- `-faccept-update`  
set WITH UPDATE clause as default for ACCEPT dest-item, instead of WITH NO UPDATE
- `-faccept-auto`  
set WITH AUTO clause as default for ACCEPT dest-item, instead of WITH TAB
- `-fconsole-is-crt`  
assume CONSOLE IS CRT if not set otherwise
- `-fno-echo-means-secure`  
NO-ECHO hides input with asterisks like SECURE
- `-fline-col-zero-default`  
assume a field DISPLAY starts at LINE 0 COL 0 (i.e. at the cursor), not LINE 1 COL 1
- `-fdisplay-special-fig-consts`  
special behaviour of DISPLAY SPACE/ALL X'01'/ALL X'02'/ALL X'07'
- `-fbinary-comp-1`  
COMP-1 is a 16-bit signed integer

`-fnumeric-pointer`  
    POINTER is a 64-bit unsigned integer

`-fmove-non-numeric-lit-to-numeric-is-zero`  
    imply zero in move of non-numeric literal to numeric items

`-fimplicit-assign-dynamic-var`  
    implicitly define a variable if an ASSIGN DYNAMIC does not match any data item

`-fcomment-paragraphs=support`  
    comment paragraphs in IDENTIFICATION DIVISION (AUTHOR, DATE-WRITTEN, ...)

`-fmemory-size-clause=support`  
    MEMORY-SIZE clause

`-fmultiple-file-tape-clause=support`  
    MULTIPLE-FILE-TAPE clause

`-flabel-records-clause=support`  
    LABEL-RECORDS clause

`-fvalue-of-clause=support`  
    VALUE-OF clause

`-fdata-records-clause=support`  
    DATA-RECORDS clause

`-ftop-level-occurs-clause=support`  
    OCCURS clause on top-level

`-fsame-as-clause=support`  
    SAME AS clause

`-ftype-to-clause=support`  
    TYPE TO clause

`-fusage-type=support`  
    USAGE type-name

`-fsynchronized-clause=support`  
    SYNCHRONIZED clause

`-fspecial-names-clause=support`  
    SPECIAL-NAMES clause

`-fgoto-statement-without-name=support`  
    GOTO statement without name

`-fstop-literal-statement=support`  
    STOP-literal statement

`-fstop-identifier-statement=support`  
    STOP-identifier statement

`-fdebugging-mode=support`  
    DEBUGGING MODE and debugging indicator

`-fuse-for-debugging=support`  
    USE FOR DEBUGGING

`-fpadding-character-clause=support`  
    PADDING CHARACTER clause

*-fnext-sentence-phrase=support*  
NEXT SENTENCE phrase

*-flisting-statements=support*  
listing-directive statements EJECT, SKIP1, SKIP2, SKIP3

*-ftitle-statement=support*  
listing-directive statement TITLE

*-fentry-statement=support*  
ENTRY statement

*-fmove-noninteger-to-alphanumeric=support*  
move noninteger to alphanumeric

*-fmove-figurative-constant-to-numeric=support*  
move figurative constants to numeric

*-fmove-figurative-space-to-numeric=support*  
move figurative constant SPACE to numeric

*-fmove-figurative-quote-to-numeric=support*  
move figurative constant QUOTE to numeric

*-fodo-without-to=support*  
OCCURS DEPENDING ON without to

*-fsection-segments=support*  
section segments

*-falter-statement=support*  
ALTER statement

*-fcall-overflow=support*  
OVERFLOW clause for CALL

*-fnumeric-boolean=support*  
boolean literals (B'1010')

*-fhexadecimal-boolean=support*  
hexadecimal-boolean literals (BX'A')

*-fnational-literals=support*  
national literals (N'UTF-16 string')

*-fhexadecimal-national-literals=support*  
hexadecimal-national literals (NX'265E')

*-fnational-character-literals=support*  
non-standard national literals (NC'UTF-16 string')

*-fhp-octal-literals=support*  
HP COBOL octal literals (%377)

*-facu-literals=support*  
ACUCOBOL-GT literals (#B #0 #H #X)

*-fword-continuation=support*  
continuation of COBOL words

*-fnot-exception-before-exception=support*  
NOT ON EXCEPTION before ON EXCEPTION

- `-facept-display-extensions=support`  
extensions to ACCEPT and DISPLAY
- `-frenames-uncommon-levels=support`  
RENAMES of 01-, 66- and 77-level items
- `-fsymbolic-constant=support`  
constants defined in SPECIAL-NAMES
- `-fconstant-78=support`  
constant with level 78 item (note: has left to right precedence in expressions)
- `-fconstant-01=support`  
constant with level 01 CONSTANT AS/FROM item
- `-fperform-varying-without-by=support`  
PERFORM VARYING without BY phrase (implies BY 1)
- `-freferance-out-of-declaratives=support`  
references to sections not in DECLARATIVES from within DECLARATIVES
- `-fprogram-prototypes=support`  
CALL/CANCEL with program-prototype-name
- `-fcall-convention-mnemonic=support`  
specifying call-convention by mnemonic
- `-fcall-convention-linkage=support`  
specifying call-convention by WITH ... LINKAGE
- `-fnumeric-value-for-edited-item=support`  
numeric literals in VALUE clause of numeric-edited items
- `-fincorrect-conf-sec-order=support`  
incorrect order of CONFIGURATION SECTION paragraphs
- `-fdefine-constant-directive=support`  
allow >> DEFINE CONSTANT var AS literal
- `-ffree-redefines-position=support`  
REDEFINES clause not following entry-name in definition
- `-frecords-mismatch-record-clause=support`  
record sizes does not match RECORD clause
- `-frecord-delimiter=support`  
RECORD DELIMITER clause
- `-fsequential-delimiters=support`  
BINARY-SEQUENTIAL and LINE-SEQUENTIAL phrases in RECORD DELIMITER
- `-frecord-delim-with-fixed-recs=support`  
RECORD DELIMITER clause on file with fixed-length records
- `-fmissing-statement=support`  
missing statement (e.g. empty IF / PERFORM)
- `-fzero-length-literals=support`  
zero-length literals, e.g. " and ""
- `-fxml-generate-extra-phrases=support`  
XML GENERATE's phrases other than COUNT IN

- fcontinue-after=*support*  
AFTER phrase in CONTINUE statement
- fgoto-entry=*support*  
ENTRY FOR GOTO and GOTO ENTRY statements
- fassign-variable=*support*  
ASSIGN [TO] variable in SELECT
- fassign-using-variable=*support*  
ASSIGN USING/VARYING variable in SELECT
- fassign-ext-dyn=*support*  
ASSIGN EXTERNAL/DYNAMIC in SELECT
- fassign-disk-from=*support*  
ASSIGN DISK FROM variable in SELECT
- fvSAM-status=*support*  
VSAM status in FILE STATUS where *support* is one of: ok, warning, archaic, obsolete, skip, ignore, error, unconformable
- fnot-reserved=*word*  
*word* to be taken out of the reserved words list
- freserved=*word*  
*word* to be added to reserved words list
- freserved=*word:alias*  
*word* to be added to reserved words list as *alias*
- fnot-register=*word*  
special register to disable
- fregister=*word*  
special register to enable

## Appendix B Reserved Words

The following list of reserved words was extracted from `cobc --list-reserved` and shows the reserved words, an implementation

**Please notice:** This list is highly specific to the option `-std=diaclect` and reserved word options (`-freserved=word`, `-fno-reserved=word`) in effect. You can get the list for a given *diaclect* by calling `cobc -std=diaclect --list-reserved`.

### B.1 Common reserved words

Reserved word	Implemented	Aliases
3-D	Yes (C/S)	
ABSENT	Yes	
ACCEPT	Yes	
ACCESS	Yes	
ACTION	Yes (C/S)	
ACTIVE-CLASS	No	
ACTIVE-X	Yes (C/S)	
ACTUAL	Yes (C/S)	
ADD	Yes	
ADDRESS	Yes	
ADJUSTABLE-COLUMNS	Yes (C/S)	
ADVANCING	Yes	
AFTER	Yes	
ALIGNED	No	
ALIGNMENT	Yes (C/S)	
ALL	Yes	
ALLOCATE	Yes	
ALLOWING	Yes (C/S)	
ALPHABET	Yes	
ALPHABETIC	Yes	
ALPHABETIC-LOWER	Yes	
ALPHABETIC-UPPER	Yes	
ALPHANUMERIC	Yes	
ALPHANUMERIC-EDITED	Yes	
ALSO	Yes	
ALTER	Yes	
ALTERNATE	Yes	
AND	Yes	
ANY	Yes	
ANYCASE	No	
APPLY	Yes (C/S)	
ARE	Yes	
AREA	Yes	AREAS
AREAS	Yes	AREA
ARGUMENT-NUMBER	Yes	
ARGUMENT-VALUE	Yes	
ARITHMETIC	Yes (C/S)	
AS	Yes	
ASCENDING	Yes	
ASCII	Yes (C/S)	

ASSIGN	Yes	
AT	Yes	
ATTRIBUTE	Yes (C/S)	
ATTRIBUTES	Yes (C/S)	
AUTO	Yes (C/S)	AUTO-SKIP, AUTOTERMINATE
AUTO-DECIMAL	Yes (C/S)	
AUTO-SKIP	Yes	AUTO, AUTOTERMINATE
AUTO-SPIN	Yes (C/S)	
AUTOMATIC	Yes	
AUTOTERMINATE	Yes	AUTO, AUTO-SKIP
AWAY-FROM-ZERO	Yes (C/S)	
B-AND	No	
B-NOT	No	
B-OR	No	
B-XOR	No	
BACKGROUND-COLOR	Yes (C/S)	BACKGROUND-COLOUR
BACKGROUND-COLOUR	Yes	BACKGROUND-COLOR
BACKGROUND-HIGH	Yes	
BACKGROUND-LOW	Yes	
BACKGROUND-STANDARD	Yes	
BAR	Yes (C/S)	
BASED	Yes	
BEEP	Yes	BELL
BEFORE	Yes	
BELL	Yes (C/S)	BEEP
BINARY	Yes	
BINARY-C-LONG	Yes	
BINARY-CHAR	Yes	
BINARY-DOUBLE	Yes	BINARY-LONG-LONG
BINARY-INT	Yes	BINARY-LONG
BINARY-LONG	Yes	BINARY-INT
BINARY-LONG-LONG	Yes	BINARY-DOUBLE
BINARY-SEQUENTIAL	Yes (C/S)	
BINARY-SHORT	Yes	
BIT	Yes	
BITMAP	Yes (C/S)	
BITMAP-END	Yes (C/S)	
BITMAP-HANDLE	Yes (C/S)	
BITMAP-NUMBER	Yes (C/S)	
BITMAP-START	Yes (C/S)	
BITMAP-TIMER	Yes (C/S)	
BITMAP-TRAILING	Yes (C/S)	
BITMAP-TRANSPARENT-COLOR	Yes (C/S)	
BITMAP-WIDTH	Yes (C/S)	
BLANK	Yes	
BLINK	Yes (C/S)	
BLOCK	Yes	
BOOLEAN	No	
BOTTOM	Yes	
BOX	Yes (C/S)	
BOXED	Yes (C/S)	
BULK-ADDITION	Yes (C/S)	

BUSY	Yes (C/S)	
BUTTONS	Yes (C/S)	
BY	Yes	
BYTE-LENGTH	Yes (C/S)	
C	Yes (C/S)	
CALENDAR-FONT	Yes (C/S)	
CALL	Yes	
CANCEL	Yes	
CANCEL-BUTTON	Yes (C/S)	
CAPACITY	Yes (C/S)	
CARD-PUNCH	Yes (C/S)	
CARD-READER	Yes (C/S)	
CASSETTE	Yes (C/S)	
CCOL	Yes (C/S)	
CD	Yes	
CELL	Yes (C/S)	CELLS
CELL-COLOR	Yes (C/S)	
CELL-DATA	Yes (C/S)	
CELL-FONT	Yes (C/S)	
CELL-PROTECTION	Yes (C/S)	
CELLS	Yes	CELL
CENTER	Yes (C/S)	
CENTERED	Yes (C/S)	
CENTERED-HEADINGS	Yes (C/S)	
CENTURY-DATE	Yes (C/S)	
CF	Yes	
CH	Yes	
CHAIN	No	
CHAINING	Yes	
CHANGED	Yes (C/S)	
CHARACTER	Yes	
CHARACTERS	Yes	
CHECK-BOX	Yes (C/S)	
CLASS	Yes	
CLASS-ID	No	
CLASSIFICATION	Yes (C/S)	
CLEAR-SELECTION	Yes (C/S)	
CLINE	Yes (C/S)	
CLINES	Yes (C/S)	
CLOSE	Yes	
COBOL	Yes (C/S)	
CODE	Yes	
CODE-SET	Yes	
COL	Yes	
COLLATING	Yes	
COLOR	Yes	
COLORS	Yes (C/S)	COLOURS
COLOURS	Yes	COLORS
COLS	Yes	
COLUMN	Yes	
COLUMN-COLOR	Yes (C/S)	
COLUMN-DIVIDERS	Yes (C/S)	

COLUMN-FONT	Yes (C/S)	
COLUMN-HEADINGS	Yes (C/S)	
COLUMN-PROTECTION	Yes (C/S)	
COLUMNS	Yes	
COMBO-BOX	Yes (C/S)	
COMMA	Yes	
COMMAND-LINE	Yes	
COMMIT	Yes	
COMMON	Yes	
COMMUNICATION	Yes	
COMP	Yes	COMPUTATIONAL
COMP-0	Yes	COMPUTATIONAL-0
COMP-1	Yes	COMPUTATIONAL-1
COMP-2	Yes	COMPUTATIONAL-2
COMP-3	Yes	COMPUTATIONAL-3
COMP-4	Yes	COMPUTATIONAL-4
COMP-5	Yes	COMPUTATIONAL-5
COMP-6	Yes	COMPUTATIONAL-6
COMP-N	Yes	COMPUTATIONAL-N
COMP-X	Yes	COMPUTATIONAL-X
COMPUTATIONAL	Yes	COMP
COMPUTATIONAL-0	Yes	COMP-0
COMPUTATIONAL-1	Yes	COMP-1
COMPUTATIONAL-2	Yes	COMP-2
COMPUTATIONAL-3	Yes	COMP-3
COMPUTATIONAL-4	Yes	COMP-4
COMPUTATIONAL-5	Yes	COMP-5
COMPUTATIONAL-6	Yes	COMP-6
COMPUTATIONAL-N	Yes	COMP-N
COMPUTATIONAL-X	Yes	COMP-X
COMPUTE	Yes	
CONDITION	Yes	
CONFIGURATION	Yes	
CONSTANT	Yes	
CONTAINS	Yes	
CONTENT	Yes	
CONTINUE	Yes	
CONTROL	Yes	
CONTROLS	Yes	
CONVERSION	Yes (C/S)	
CONVERTING	Yes	
COPY	Yes	
COPY-SELECTION	Yes (C/S)	
CORE-INDEX	Yes (C/S)	
CORR	Yes	CORRESPONDING
CORRESPONDING	Yes	CORR
COUNT	Yes	
CRT	Yes	
CRT-UNDER	Yes	
CSize	Yes (C/S)	
CURRENCY	Yes	
CURSOR	Yes	

CURSOR-COL	Yes (C/S)	
CURSOR-COLOR	Yes (C/S)	
CURSOR-FRAME-WIDTH	Yes (C/S)	
CURSOR-ROW	Yes (C/S)	
CURSOR-X	Yes (C/S)	
CURSOR-Y	Yes (C/S)	
CUSTOM-PRINT-TEMPLATE	Yes (C/S)	
CYCLE	Yes (C/S)	
CYL-INDEX	Yes (C/S)	
CYL-OVERFLOW	Yes (C/S)	
DASHED	Yes (C/S)	
DATA	Yes	
DATA-COLUMNS	Yes (C/S)	
DATA-POINTER	No	
DATA-TYPES	Yes (C/S)	
DATE	Yes	
DATE-ENTRY	Yes (C/S)	
DAY	Yes	
DAY-OF-WEEK	Yes	
DE	Yes	
DEBUGGING	Yes	
DECIMAL-POINT	Yes	
DECLARATIVES	Yes	
DEFAULT	Yes	
DEFAULT-BUTTON	Yes (C/S)	
DEFAULT-FONT	Yes	
DELETE	Yes	
DELIMITED	Yes	
DELIMITER	Yes	
DEPENDING	Yes	
DESCENDING	Yes	
DESTINATION	Yes	
DESTROY	Yes	
DETAIL	Yes	
DISABLE	Yes	
DISC	Yes (C/S)	
DISK	Yes (C/S)	
DISP	Yes (C/S)	
DISPLAY	Yes	
DISPLAY-COLUMNS	Yes (C/S)	
DISPLAY-FORMAT	Yes (C/S)	
DIVIDE	Yes	
DIVIDER-COLOR	Yes (C/S)	
DIVIDERS	Yes (C/S)	
DIVISION	Yes	
DOTDASH	Yes (C/S)	
DOTTED	Yes (C/S)	
DOUBLE	Yes	FLOAT-LONG
DOWN	Yes	
DRAG-COLOR	Yes (C/S)	
DROP-DOWN	Yes (C/S)	
DROP-LIST	Yes (C/S)	

DUPLICATES	Yes	
DYNAMIC	Yes	
EBCDIC	Yes (C/S)	
EC	Yes	
ECHO	Yes	
EGI	Yes	
ELEMENT	Yes (C/S)	
ELSE	Yes	
EMI	Yes	
EMPTY-CHECK	Yes	REQUIRED
ENABLE	Yes	
ENCODING	Yes (C/S)	
ENCRYPTION	Yes (C/S)	
END	Yes	
END-ACCEPT	Yes	
END-ADD	Yes	
END-CALL	Yes	
END-CHAIN	No	
END-COLOR	Yes (C/S)	
END-COMPUTE	Yes	
END-DELETE	Yes	
END-DISPLAY	Yes	
END-DIVIDE	Yes	
END-EVALUATE	Yes	
END-IF	Yes	
END-JSON	Yes	
END-MODIFY	Yes (C/S)	
END-MULTIPLY	Yes	
END-OF-PAGE	Yes	EOP
END-PERFORM	Yes	
END-READ	Yes	
END-RECEIVE	Yes	
END-RETURN	Yes	
END-REWRITE	Yes	
END-SEARCH	Yes	
END-START	Yes	
END-STRING	Yes	
END-SUBTRACT	Yes	
END-UNSTRING	Yes	
END-WRITE	Yes	
END-XML	Yes	
ENGRAVED	Yes (C/S)	
ENSURE-VISIBLE	Yes (C/S)	
ENTRY	Yes	
ENTRY-CONVENTION	Yes (C/S)	
ENTRY-FIELD	Yes (C/S)	
ENTRY-REASON	Yes (C/S)	
ENVIRONMENT	Yes	
ENVIRONMENT-NAME	Yes	
ENVIRONMENT-VALUE	Yes	
EO	No	
EOL	Yes (C/S)	

EOP	Yes	END-OF-PAGE
EOS	Yes (C/S)	
EQUAL	Yes	EQUALS
EQUALS	Yes	EQUAL
ERASE	Yes (C/S)	
ERROR	Yes	
ESCAPE	Yes	
ESCAPE-BUTTON	Yes (C/S)	
ESI	Yes	
EVALUATE	Yes	
EVENT	Yes	
EVENT-LIST	Yes (C/S)	
EVERY	Yes (C/S)	
EXCEPTION	Yes	
EXCEPTION-OBJECT	No	
EXCEPTION-VALUE	Yes (C/S)	
EXCLUSIVE	Yes	
EXHIBIT	Yes	
EXIT	Yes	
EXPAND	Yes (C/S)	
EXPANDS	No (C/S)	
EXTEND	Yes	
EXTENDED-SEARCH	Yes (C/S)	
EXTERN	Yes (C/S)	
EXTERNAL	Yes	
EXTERNAL-FORM	Yes	
F	Yes (C/S)	
FACTORY	No	
FALSE	Yes	
FD	Yes	
FH--FCD	Yes (C/S)	
FH--KEYDEF	Yes (C/S)	
FILE	Yes	
FILE-CONTROL	Yes	
FILE-ID	Yes	
FILE-LIMIT	Yes (C/S)	
FILE-LIMITS	Yes (C/S)	
FILE-NAME	Yes (C/S)	
FILE-POS	Yes (C/S)	
FILL-COLOR	Yes (C/S)	
FILL-COLOR2	Yes (C/S)	
FILL-PERCENT	Yes (C/S)	
FILLER	Yes	
FINAL	Yes	
FINISH-REASON	Yes (C/S)	
FIRST	Yes	
FIXED	Yes	
FIXED-FONT	Yes	
FIXED-WIDTH	Yes (C/S)	
FLAT	Yes (C/S)	
FLAT-BUTTONS	Yes (C/S)	
FLOAT	Yes	FLOAT-SHORT

FLOAT-BINARY-128	No	
FLOAT-BINARY-32	No	
FLOAT-BINARY-64	No	
FLOAT-DECIMAL-16	Yes	
FLOAT-DECIMAL-34	Yes	
FLOAT-EXTENDED	No	
FLOAT-INFINITY	No	
FLOAT-LONG	Yes	DOUBLE
FLOAT-NOT-A-NUMBER	No (C/S)	
FLOAT-SHORT	Yes	FLOAT
FLOATING	Yes	
FONT	Yes	
FOOTING	Yes	
FOR	Yes	
FOREGROUND-COLOR	Yes (C/S)	FOREGROUND-COLOUR
FOREGROUND-COLOUR	Yes	FOREGROUND-COLOR
FOREVER	Yes (C/S)	
FORMAT	No	
FRAME	Yes (C/S)	
FRAMED	Yes (C/S)	
FREE	Yes	
FROM	Yes	
FULL	Yes (C/S)	LENGTH-CHECK
FULL-HEIGHT	Yes (C/S)	
FUNCTION	Yes	
FUNCTION-ID	Yes	
FUNCTION-POINTER	No	
GENERATE	Yes	
GET	No	
GIVING	Yes	
GLOBAL	Yes	
GO	Yes	
GO-BACK	Yes (C/S)	
GO-FORWARD	Yes (C/S)	
GO-HOME	Yes (C/S)	
GO-SEARCH	Yes (C/S)	
GOBACK	Yes	
GRAPHICAL	Yes (C/S)	
GREATER	Yes	
GRID	Yes (C/S)	
GROUP	Yes	
GROUP-USAGE	No	
GROUP-VALUE	Yes (C/S)	
HANDLE	Yes	
HAS-CHILDREN	Yes (C/S)	
HEADING	Yes	
HEADING-COLOR	Yes (C/S)	
HEADING-DIVIDER-COLOR	Yes (C/S)	
HEADING-FONT	Yes (C/S)	
HEAVY	Yes (C/S)	
HEIGHT-IN-CELLS	Yes (C/S)	
HIDDEN-DATA	Yes (C/S)	

HIGH-COLOR	Yes (C/S)	
HIGH-VALUE	Yes	HIGH-VALUES
HIGH-VALUES	Yes	HIGH-VALUE
HIGHLIGHT	Yes (C/S)	
HOT-TRACK	Yes (C/S)	
HSCROLL	Yes (C/S)	
HSCROLL-POS	Yes (C/S)	
I-O	Yes	
I-O-CONTROL	Yes	
ICON	Yes (C/S)	
ID	Yes	
IDENTIFICATION	Yes	
IDENTIFIED	Yes	
IF	Yes	
IGNORE	Yes	
IGNORING	Yes (C/S)	
IMPLEMENTS	No (C/S)	
IN	Yes	
INDEPENDENT	Yes (C/S)	
INDEX	Yes	
INDEXED	Yes	
INDICATE	Yes	
INHERITS	No	
INITIAL	Yes	
INITIALISE	Yes	INITIALIZE
INITIALISED	Yes	INITIALIZED
INITIALIZE	Yes	INITIALISE
INITIALIZED	Yes (C/S)	INITIALISED
INITIATE	Yes	
INPUT	Yes	
INPUT-OUTPUT	Yes	
INQUIRE	Yes	
INSERT-ROWS	Yes (C/S)	
INSERTION-INDEX	Yes (C/S)	
INSPECT	Yes	
INTERFACE	No	
INTERFACE-ID	No	
INTERMEDIATE	Yes (C/S)	
INTO	Yes	
INTRINSIC	Yes (C/S)	
INVALID	Yes	
INVOKE	No	
IS	Yes	
ITEM	Yes (C/S)	
ITEM-TEXT	Yes (C/S)	
ITEM-TO-ADD	Yes (C/S)	
ITEM-TO-DELETE	Yes (C/S)	
ITEM-TO-EMPTY	Yes (C/S)	
ITEM-VALUE	Yes (C/S)	
JSON	Yes	
JUST	Yes	JUSTIFIED
JUSTIFIED	Yes	JUST

KEPT	Yes	
KEY	Yes	
KEYBOARD	Yes (C/S)	
LABEL	Yes	
LABEL-OFFSET	Yes (C/S)	
LARGE-FONT	Yes	
LARGE-OFFSET	Yes (C/S)	
LAST	Yes	
LAST-ROW	Yes (C/S)	
LAYOUT-DATA	Yes (C/S)	
LAYOUT-MANAGER	Yes	
LC_ALL	No (C/S)	
LC_COLLATE	No (C/S)	
LC_CTYPE	No (C/S)	
LC_MESSAGES	No (C/S)	
LC_MONETARY	No (C/S)	
LC_NUMERIC	No (C/S)	
LC_TIME	No (C/S)	
LEADING	Yes	
LEADING-SHIFT	Yes (C/S)	
LEAVE	Yes (C/S)	
LEFT	Yes	
LEFT-JUSTIFY	No	
LEFT-TEXT	Yes (C/S)	
LEFTLINE	Yes	
LENGTH	Yes	
LENGTH-CHECK	Yes	FULL
LESS	Yes	
LIKE	Yes	
LIMIT	Yes	
LIMITS	Yes	
LINAGE	Yes	
LINAGE-COUNTER	Yes	
LINE	Yes	
LINE-COUNTER	Yes	
LINE-SEQUENTIAL	Yes (C/S)	
LINES	Yes	
LINES-AT-ROOT	Yes (C/S)	
LINKAGE	Yes	
LIST-BOX	Yes (C/S)	
LM-RESIZE	Yes	
LOC	Yes (C/S)	
LOCAL-STORAGE	Yes	
LOCALE	Yes	
LOCK	Yes	
LOCK-HOLDING	Yes (C/S)	
LONG-DATE	Yes (C/S)	
LOW-COLOR	Yes (C/S)	
LOW-VALUE	Yes	LOW-VALUES
LOW-VALUES	Yes	LOW-VALUE
LOWER	Yes (C/S)	
LOWERED	Yes (C/S)	

LOWLIGHT	Yes (C/S)
MAGNETIC-TAPE	Yes (C/S)
MANUAL	Yes
MASS-UPDATE	Yes (C/S)
MASTER-INDEX	Yes (C/S)
MAX-LINES	Yes (C/S)
MAX-PROGRESS	Yes (C/S)
MAX-TEXT	Yes (C/S)
MAX-VAL	Yes (C/S)
MEDIUM-FONT	Yes
MEMORY	Yes (C/S)
MENU	Yes
MERGE	Yes
MESSAGE	Yes
METHOD	No
METHOD-ID	No
MIN-VAL	Yes (C/S)
MINUS	Yes
MODE	Yes
MODIFY	Yes
MODULES	Yes (C/S)
MOVE	Yes
MULTILINE	Yes (C/S)
MULTIPLE	Yes
MULTIPLY	Yes
NAME	Yes (C/S)
NAMED	Yes (C/S)
NAMESPACE	Yes (C/S)
NAMESPACE-PREFIX	Yes (C/S)
NATIONAL	Yes
NATIONAL-EDITED	Yes
NATIVE	Yes
NAVIGATE-URL	Yes (C/S)
NEAREST-AWAY-FROM-ZERO	Yes (C/S)
NEAREST-EVEN	Yes (C/S)
NEAREST-TOWARD-ZERO	Yes (C/S)
NEGATIVE	Yes
NESTED	Yes
NEW	Yes
NEXT	Yes
NEXT-ITEM	Yes (C/S)
NO	Yes
NO-AUTO-DEFAULT	Yes (C/S)
NO-AUTOSEL	Yes (C/S)
NO-BOX	Yes (C/S)
NO-DIVIDERS	Yes (C/S)
NO-ECHO	Yes
NO-F4	Yes (C/S)
NO-FOCUS	Yes (C/S)
NO-GROUP-TAB	Yes (C/S)
NO-KEY-LETTER	Yes (C/S)
NO-SEARCH	Yes (C/S)

NO-UPDOWN	Yes (C/S)	
NOMINAL	Yes (C/S)	
NONE	No (C/S)	
NONNUMERIC	Yes (C/S)	
NORMAL	Yes (C/S)	
NOT	Yes	
NOTAB	Yes (C/S)	
NOTHING	Yes	
NOTIFY	Yes (C/S)	
NOTIFY-CHANGE	Yes (C/S)	
NOTIFY-DBLCLICK	Yes (C/S)	
NOTIFY-SELCHANGE	Yes (C/S)	
NULL	Yes	NULLS
NULLS	Yes	NULL
NUM-COL-HEADINGS	Yes (C/S)	
NUM-ROWS	Yes (C/S)	
NUMBER	Yes	
NUMBERS	Yes	
NUMERIC	Yes	
NUMERIC-EDITED	Yes	
OBJECT	Yes	
OBJECT-COMPUTER	Yes	
OBJECT-REFERENCE	No	
OCCURS	Yes	
OF	Yes	
OFF	Yes	
OK-BUTTON	Yes (C/S)	
OMITTED	Yes	
ON	Yes	
ONLY	Yes	
OPEN	Yes	
OPTIONAL	Yes	
OPTIONS	Yes	
OR	Yes	
ORDER	Yes	
ORGANISATION	Yes	ORGANIZATION
ORGANIZATION	Yes	ORGANISATION
OTHER	Yes	
OTHERS	Yes (C/S)	
OUTPUT	Yes	
OVERFLOW	Yes	
OVERLAP-LEFT	Yes (C/S)	OVERLAP-TOP
OVERLAP-TOP	Yes (C/S)	OVERLAP-LEFT
OVERLINE	Yes	
OVERRIDE	No	
PACKED-DECIMAL	Yes	
PADDING	Yes	
PAGE	Yes	
PAGE-COUNTER	Yes	
PAGE-SETUP	Yes (C/S)	
PAGED	Yes (C/S)	
PARAGRAPH	Yes (C/S)	

PARENT	Yes (C/S)	
PARSE	Yes (C/S)	
PASCAL	Yes (C/S)	
PASSWORD	Yes (C/S)	
PERFORM	Yes	
PERMANENT	Yes (C/S)	
PF	Yes	
PH	Yes	
PHYSICAL	Yes	
PIC	Yes	PICTURE
PICTURE	Yes	PIC
PIXEL	Yes (C/S)	PIXELS
PIXELS	Yes	PIXEL
PLACEMENT	Yes (C/S)	
PLUS	Yes	
POINTER	Yes	
POP-UP	Yes (C/S)	
POS	Yes	
POSITION	Yes	
POSITION-SHIFT	Yes (C/S)	
POSITIVE	Yes	
PREFIXED	No (C/S)	
PRESENT	Yes	
PREVIOUS	Yes (C/S)	
PRINT	Yes (C/S)	
PRINT-NO-PROMPT	Yes (C/S)	
PRINT-PREVIEW	Yes (C/S)	
PRINTER	Yes (C/S)	
PRINTER-1	Yes (C/S)	
PRINTING	Yes	
PRIORITY	Yes	
PROCEDURE	Yes	
PROCEDURE-POINTER	Yes	PROGRAM-POINTER
PROCEDURES	Yes	
PROCEED	Yes	
PROCESSING	Yes (C/S)	
PROGRAM	Yes	
PROGRAM-ID	Yes	
PROGRAM-POINTER	Yes	PROCEDURE-POINTER
PROGRESS	Yes (C/S)	
PROHIBITED	Yes (C/S)	
PROMPT	Yes	
PROPERTIES	Yes (C/S)	
PROPERTY	Yes	
PROTECTED	Yes (C/S)	
PROTOTYPE	No	
PURGE	Yes	
PUSH-BUTTON	Yes (C/S)	
QUERY-INDEX	Yes (C/S)	
QUEUE	Yes	
QUOTE	Yes	QUOTES
QUOTES	Yes	QUOTE

RADIO-BUTTON	Yes (C/S)	
RAISE	Yes	
RAISED	Yes (C/S)	
RAISING	No	
RANDOM	Yes	
RD	Yes	
READ	Yes	
READ-ONLY	Yes (C/S)	
READERS	Yes (C/S)	
RECEIVE	Yes	
RECORD	Yes	
RECORD-DATA	Yes (C/S)	
RECORD-OVERFLOW	Yes (C/S)	
RECORD-TO-ADD	Yes (C/S)	
RECORD-TO-DELETE	Yes (C/S)	
RECORDING	Yes	
RECORDS	Yes	
RECURSIVE	Yes (C/S)	
REDEFINES	Yes	
REEL	Yes	
REFERENCE	Yes	
REFERENCES	Yes	
REFRESH	Yes (C/S)	
REGION-COLOR	Yes (C/S)	
RELATION	No (C/S)	
RELATIVE	Yes	
RELEASE	Yes	
REMAINDER	Yes	
REMOVAL	Yes	
RENAMES	Yes	
REORG-CRITERIA	Yes (C/S)	
REPLACE	Yes	
REPLACING	Yes	
REPORT	Yes	
REPORTING	Yes	
REPORTS	Yes	
REPOSITORY	Yes	
REQUIRED	Yes (C/S)	EMPTY-CHECK
REREAD	Yes (C/S)	
RERUN	Yes (C/S)	
RESERVE	Yes	
RESET	Yes	
RESET-GRID	Yes (C/S)	
RESET-LIST	Yes (C/S)	
RESET-TABS	Yes (C/S)	
RESUME	No	
RETRY	Yes	
RETURN	Yes	
RETURNING	Yes	
REVERSE	Yes	
REVERSE-VIDEO	Yes (C/S)	
REVERSED	Yes	

REWIND	Yes
REWRITE	Yes
RF	Yes
RH	Yes
RIGHT	Yes
RIGHT-ALIGN	Yes (C/S)
RIGHT-JUSTIFY	No
RIMMED	Yes (C/S)
ROLLBACK	Yes
ROUNDED	Yes
ROUNDING	Yes (C/S)
ROW-COLOR	Yes (C/S)
ROW-COLOR-PATTERN	Yes (C/S)
ROW-DIVIDERS	Yes (C/S)
ROW-FONT	Yes (C/S)
ROW-HEADINGS	Yes (C/S)
ROW-PROTECTION	Yes (C/S)
RUN	Yes
S	Yes (C/S)
SAME	Yes
SAVE-AS	Yes (C/S)
SAVE-AS-NO-PROMPT	Yes (C/S)
SCREEN	Yes
SCROLL	Yes (C/S)
SCROLL-BAR	Yes (C/S)
SD	Yes
SEARCH	Yes
SEARCH-OPTIONS	Yes (C/S)
SEARCH-TEXT	Yes (C/S)
SECONDS	Yes (C/S)
SECTION	Yes
SECURE	Yes (C/S)
SEGMENT	Yes
SEGMENT-LIMIT	Yes
SELECT	Yes
SELECT-ALL	Yes (C/S)
SELECTION-INDEX	Yes (C/S)
SELECTION-TEXT	Yes (C/S)
SELF	No
SELF-ACT	Yes (C/S)
SEND	Yes
SENTENCE	Yes
SEPARATE	Yes
SEPARATION	Yes (C/S)
SEQUENCE	Yes
SEQUENTIAL	Yes
SET	Yes
SHADING	Yes (C/S)
SHADOW	Yes (C/S)
SHARING	Yes
SHORT-DATE	Yes (C/S)
SHOW-LINES	Yes (C/S)

SHOW-NONE	Yes (C/S)	
SHOW-SEL-ALWAYS	Yes (C/S)	
SIGN	Yes	
SIGNED	Yes	
SIGNED-INT	Yes	
SIGNED-LONG	Yes	
SIGNED-SHORT	Yes	
SIZE	Yes	
SMALL-FONT	Yes	
SORT	Yes	
SORT-MERGE	Yes	
SORT-ORDER	Yes (C/S)	
SOURCE	Yes	
SOURCE-COMPUTER	Yes	
SOURCES	No	
SPACE	Yes	SPACES
SPACE-FILL	No	
SPACES	Yes	SPACE
SPECIAL-NAMES	Yes	
SPINNER	Yes (C/S)	
SQUARE	Yes (C/S)	
STANDARD	Yes	
STANDARD-1	Yes	
STANDARD-2	Yes	
STANDARD-BINARY	Yes (C/S)	
STANDARD-DECIMAL	Yes (C/S)	
START	Yes	
START-X	Yes (C/S)	
START-Y	Yes (C/S)	
STATEMENT	No (C/S)	
STATIC	Yes (C/S)	
STATIC-LIST	Yes (C/S)	
STATUS	Yes	
STATUS-BAR	Yes (C/S)	
STATUS-TEXT	Yes (C/S)	
STDCALL	Yes (C/S)	
STEP	Yes (C/S)	
STOP	Yes	
STRING	Yes	
STRONG	Yes (C/S)	
STYLE	Yes (C/S)	
SUB-QUEUE-1	Yes	
SUB-QUEUE-2	Yes	
SUB-QUEUE-3	Yes	
SUBTRACT	Yes	
SUBWINDOW	Yes	
SUM	Yes	
SUPER	No	
SUPPRESS	Yes	
SYMBOL	No (C/S)	
SYMBOLIC	Yes	
SYNC	Yes	SYNCHRONISED, SYNCHRONIZED

SYNCHRONISED	Yes	SYNC, SYNCHRONIZED
SYNCHRONIZED	Yes	SYNC, SYNCHRONISED
SYSTEM-DEFAULT	Yes	
SYSTEM-INFO	Yes (C/S)	
SYSTEM-OFFSET	Yes	
TAB	Yes (C/S)	
TAB-TO-ADD	Yes (C/S)	
TAB-TO-DELETE	Yes (C/S)	
TABLE	Yes	
TALLYING	Yes	
TAPE	Yes (C/S)	
TEMPORARY	Yes (C/S)	
TERMINAL-INFO	Yes (C/S)	
TERMINATE	Yes	
TERMINATION-VALUE	Yes (C/S)	
TEST	Yes	
TEXT	Yes	
THAN	Yes	
THEN	Yes	
THREAD	Yes	
THREADS	Yes	
THROUGH	Yes	THRU
THRU	Yes	THROUGH
THUMB-POSITION	Yes (C/S)	
TILED-HEADINGS	Yes (C/S)	
TIME	Yes	
TIME-OUT	Yes (C/S)	TIMEOUT
TIMEOUT	Yes	TIME-OUT
TIMES	Yes	
TITLE	Yes (C/S)	
TITLE-POSITION	Yes (C/S)	
TO	Yes	
TOP	Yes	
TOWARD-GREATER	Yes (C/S)	
TOWARD-LESSER	Yes (C/S)	
TRACK	Yes (C/S)	
TRACK-AREA	Yes (C/S)	
TRACK-LIMIT	Yes (C/S)	
TRACKS	Yes (C/S)	
TRADITIONAL-FONT	Yes	
TRAILING	Yes	
TRAILING-SHIFT	Yes (C/S)	
TRAILING-SIGN	No	
TRANSFORM	Yes	
TRANSPARENT	Yes (C/S)	
TREE-VIEW	Yes (C/S)	
TRUE	Yes	
TRUNCATION	Yes (C/S)	
TYPE	Yes	
TYPDEF	Yes	
U	Yes (C/S)	
UCS-4	Yes (C/S)	

UNBOUNDED	Yes (C/S)	
UNDERLINE	Yes (C/S)	
UNFRAMED	Yes (C/S)	
UNIT	Yes	
UNIVERSAL	No	
UNLOCK	Yes	
UNSIGNED	Yes	
UNSIGNED-INT	Yes	
UNSIGNED-LONG	Yes	
UNSIGNED-SHORT	Yes	
UNSORTED	Yes (C/S)	
UNSTRING	Yes	
UNTIL	Yes	
UP	Yes	
UPDATE	Yes	
UPDATERS	Yes (C/S)	
UPON	Yes	
UPPER	Yes (C/S)	
USAGE	Yes	
USE	Yes	
USE-ALT	Yes (C/S)	
USE-RETURN	Yes (C/S)	
USE-TAB	Yes (C/S)	
USER	Yes (C/S)	
USER-DEFAULT	Yes	
USING	Yes	
UTF-16	Yes (C/S)	
UTF-8	Yes (C/S)	
V	Yes (C/S)	
VAL-STATUS	No	
VALID	No	
VALIDATE	Yes	
VALIDATE-STATUS	No	
VALIDATING	Yes (C/S)	
VALUE	Yes	VALUES
VALUE-FORMAT	Yes (C/S)	
VALUES	Yes	VALUE
VARIABLE	Yes (C/S)	
VARIANT	Yes	
VARYING	Yes	
VERTICAL	Yes (C/S)	
VERY-HEAVY	Yes (C/S)	
VIRTUAL-WIDTH	Yes (C/S)	
VOLATILE	Yes	
VPADDING	Yes (C/S)	
VSCROLL	Yes (C/S)	
VSCROLL-BAR	Yes (C/S)	
VSCROLL-POS	Yes (C/S)	
VTOP	Yes (C/S)	
WAIT	Yes	
WEB-BROWSER	Yes (C/S)	
WHEN	Yes	

WIDTH	Yes (C/S)	
WIDTH-IN-CELLS	Yes (C/S)	
WINDOW	Yes	
WITH	Yes	
WORDS	Yes	
WORKING-STORAGE	Yes	
WRAP	Yes (C/S)	
WRITE	Yes	
WRITE-ONLY	Yes (C/S)	
WRITE-VERIFY	Yes (C/S)	
WRITERS	Yes (C/S)	
X	Yes (C/S)	
XML	Yes	
XML-DECLARATION	Yes (C/S)	
Y	Yes (C/S)	
YYYYDDD	Yes (C/S)	
YYYYMMDD	Yes (C/S)	
ZERO	Yes	ZEROES, ZEROS
ZERO-FILL	No (C/S)	
ZEROES	Yes	ZERO, ZEROS
ZEROS	Yes	ZERO, ZEROES

## B.2 Extra (obsolete) context sensitive words

AUTHOR, DATE-COMPILED, DATE-MODIFIED, DATE-WRITTEN, INSTALLATION, REMARKS, SECURITY

## B.3 Internal registers

Register	Implemented	Definition
'ADDRESS OF' phrase	Yes	USAGE POINTER
COB-CRT-STATUS	Yes	PICTURE 9(4) USAGE DISPLAY VALUE ZERO
DEBUG-ITEM	Yes	PICTURE X(n) USAGE DISPLAY
'LENGTH OF' phrase	Yes	CONSTANT USAGE BINARY-LONG
NUMBER-OF-CALL-PARAMETERS	Yes	USAGE BINARY-LONG
RETURN-CODE	Yes	GLOBAL USAGE BINARY-LONG VALUE ZERO
SORT-RETURN	Yes	GLOBAL USAGE BINARY-LONG VALUE ZERO
TALLY	Yes	GLOBAL PICTURE 9(5) USAGE BINARY VALUE ZERO
WHEN-COMPILED	Yes	CONSTANT PICTURE X(16) USAGE DISPLAY
XML-CODE	Yes	GLOBAL PICTURE S9(9) USAGE BINARY VALUE 0
JSON-CODE	Yes	GLOBAL PICTURE S9(9) USAGE BINARY VALUE 0

## Appendix C Intrinsic Functions

The following list of intrinsic functions was extracted from `cobc --list-intrinsics` and shows the names of the available functions, an implementation note and the number of parameters.

<b>Intrinsic</b>	<b>Function</b>	<b>Implemented</b>
ABS	Yes	1
ACOS	Yes	1
ANNUITY	Yes	2
ASIN	Yes	1
ATAN	Yes	1
BOOLEAN-OF-INTEGER	No	2
BYTE-LENGTH	Yes	1
CHAR	Yes	1
CHAR-NATIONAL	No	1
COMBINED-DATETIME	Yes	2
CONCAT	Yes	Unlimited
CONCATENATE	Yes	Unlimited
CONTENT-LENGTH	Yes	1
CONTENT-OF	Yes	1
COS	Yes	1
CURRENCY-SYMBOL	Yes	0
CURRENT-DATE	Yes	0
DATE-OF-INTEGER	Yes	1
DATE-TO-YYYYMMDD	Yes	1
DAY-OF-INTEGER	Yes	1
DAY-TO-YYYYDDD	Yes	1
DISPLAY-OF	No	1
E	Yes	0
EXCEPTION-FILE	Yes	0
EXCEPTION-FILE-N	No	0
EXCEPTION-LOCATION	Yes	0
EXCEPTION-LOCATION-N	No	0
EXCEPTION-STATEMENT	Yes	0
EXCEPTION-STATUS	Yes	0
EXP	Yes	1
EXP10	Yes	1
FACTORIAL	Yes	1
FORMATTED-CURRENT-DATE	Yes	1
FORMATTED-DATE	Yes	2
FORMATTED-DATETIME	Yes	4
FORMATTED-TIME	Yes	3
FRACTION-PART	Yes	1
HIGHEST-ALGEBRAIC	Yes	1
INTEGER	Yes	1
INTEGER-OF-BOOLEAN	No	1
INTEGER-OF-DATE	Yes	1
INTEGER-OF-DAY	Yes	1
INTEGER-OF-FORMATTED-DATE	Yes	2
INTEGER-PART	Yes	1
LENGTH	Yes	1
LENGTH-AN	Yes	1

LOCALE-COMPARE	Yes	2
LOCALE-DATE	Yes	1
LOCALE-TIME	Yes	1
LOCALE-TIME-FROM-SECONDS	Yes	1
LOG	Yes	1
LOG10	Yes	1
LOWER-CASE	Yes	1
LOWEST-ALGEBRAIC	Yes	1
MAX	Yes	Unlimited
MEAN	Yes	Unlimited
MEDIAN	Yes	Unlimited
MIDRANGE	Yes	Unlimited
MIN	Yes	Unlimited
MOD	Yes	2
MODULE-CALLER-ID	Yes	0
MODULE-DATE	Yes	0
MODULE-FORMATTED-DATE	Yes	0
MODULE-ID	Yes	0
MODULE-PATH	Yes	0
MODULE-SOURCE	Yes	0
MODULE-TIME	Yes	0
MONETARY-DECIMAL-POINT	Yes	0
MONETARY-THOUSANDS-SEPARATOR	Yes	0
NATIONAL-OF	No	1
NUMERIC-DECIMAL-POINT	Yes	0
NUMERIC-THOUSANDS-SEPARATOR	Yes	0
NUMVAL	Yes	1
NUMVAL-C	Yes	2
NUMVAL-F	Yes	1
ORD	Yes	1
ORD-MAX	Yes	Unlimited
ORD-MIN	Yes	Unlimited
PI	Yes	0
PRESENT-VALUE	Yes	Unlimited
RANDOM	Yes	0
RANGE	Yes	Unlimited
REM	Yes	2
REVERSE	Yes	1
SECONDS-FROM-FORMATTED-TIME	Yes	2
SECONDS-PAST-MIDNIGHT	Yes	0
SIGN	Yes	1
SIN	Yes	1
SQRT	Yes	1
STANDARD-COMPARE	No	2
STANDARD-DEVIATION	Yes	Unlimited
STORED-CHAR-LENGTH	Yes	1
SUBSTITUTE	Yes	Unlimited
SUBSTITUTE-CASE	Yes	Unlimited
SUM	Yes	Unlimited
TAN	Yes	1
TEST-DATE-YYYYMMDD	Yes	1
TEST-DAY-YYYYDDD	Yes	1

TEST-FORMATTED-DATETIME	Yes	2
TEST-NUMVAL	Yes	1
TEST-NUMVAL-C	Yes	2
TEST-NUMVAL-F	Yes	1
TRIM	Yes	1
UPPER-CASE	Yes	1
VARIANCE	Yes	Unlimited
WHEN-COMPILED	Yes	0
YEAR-TO-YYYY	Yes	1

## Appendix D System routines

The following list of system routines was extracted from `cobc --list-system` and shows the names of the available system routines along with the number of parameters.

System routine	Parameters
SYSTEM	1
CBL_AND	3
CBL_ALARM_SOUND	0
CBL_BELL_SOUND	0
CBL_CHANGE_DIR	1
CBL_CHECK_FILE_EXIST	2
CBL_CLOSE_FILE	1
CBL_COPY_FILE	2
CBL_CREATE_DIR	1
CBL_CREATE_FILE	5
CBL_DELETE_DIR	1
CBL_DELETE_FILE	1
CBL_EQ	3
CBL_ERROR_PROC	2
CBL_EXIT_PROC	2
CBL_FLUSH_FILE	1
CBL_GET_CSR_POS	1
CBL_GET_CURRENT_DIR	3
CBL_GET_SCR_SIZE	2
CBL_IMP	3
CBL_NIMP	3
CBL_NOR	3
CBL_NOT	2
CBL_OPEN_FILE	5
CBL_OR	3
CBL_READ_FILE	5
CBL_READ_KBD_CHAR	1
CBL_RENAME_FILE	2
CBL_SET_CSR_POS	1
CBL_TOLOWER	2
CBL_Toupper	2
CBL_WRITE_FILE	5
CBL_XOR	3
CBL_GC_FORK	0
CBL_GC_GETOPT	6
CBL_GC_HOSTED	2
CBL_GC_NANOSLEEP	1
CBL_GC_PRINTABLE	1 - 2
CBL_GC_WAITPID	1
CBL_OC_GETOPT	6
CBL_OC_HOSTED	2
CBL_OC_NANOSLEEP	1
C\$CALLED BY	1
C\$CHDIR	2
C\$COPY	3
C\$DELETE	2

C\$FILEINFO	2
C\$GETPID	0
C\$JUSTIFY	1 - 2
C\$MAKEDIR	1
C\$NARG	1
C\$PARAMSIZE	1
C\$PRINTABLE	1 - 2
C\$SLEEP	1
C\$TOLOWER	2
C\$TOUPPER	2
EXTFH	2
X"91"	3
X"E4"	0
X"E5"	0
X"F4"	2
X"F5"	2

## Appendix E System names

The following list of system names was extracted from `cobc --list-mnemonics` and shows the system names categorized by their type.

### E.1 System names: device

SYSIN, SYSIPT, STDIN, SYSOUT, SYSLIST, SYSLST, SYSPCH, SYSPUNCH, STDOUT, PRINT, PRINTER, PRINTER-1, SYSERR, STDERR, CONSOLE

### E.2 System names: feature

C01, C02, C03, C04, C05, C06, C07, C08, C09, C10, C11, C12, S01, S02, S03, S04, S05, CSP, FORMFEED, TOP, CALL-CONVENTION

### E.3 System names: switch

SWITCH-0, SWITCH-1, SWITCH-2, SWITCH-3, SWITCH-4, SWITCH-5, SWITCH-6, SWITCH-7, SWITCH-8, SWITCH-9, SWITCH-10, SWITCH-11, SWITCH-12, SWITCH-13, SWITCH-14, SWITCH-15, SWITCH-16, SWITCH-17, SWITCH-18, SWITCH-19, SWITCH-20, SWITCH-21, SWITCH-22, SWITCH-23, SWITCH-24, SWITCH-25, SWITCH-26, SWITCH-27, SWITCH-28, SWITCH-29, SWITCH-30, SWITCH-31, SWITCH-32, SWITCH-33, SWITCH-34, SWITCH-35, SWITCH-36

## Appendix F Compiler Configuration

The following list was extracted from `config/default.conf`.

```
# Value: any string
name: "GnuCOBOL"

# Value: enum
standard-define                0
#     CB_STD_GC = 0,
#     CB_STD_MF,
#     CB_STD_IBM,
#     CB_STD_MVS,
#     CB_STD_BS2000,
#     CB_STD_ACU,
#     CB_STD_85,
#     CB_STD_2002,
#     CB_STD_2014

# Value: int
tab-width:                     8
text-column:                   72
# Maximum word-length for COBOL words / Programmer defined words
# Be aware that GC checks the word length against COB_MAX_WORDLEN
# first (currently 63)
word-length:                   63

# Maximum literal size in general
literal-length:                8191

# Maximum numeric literal size (absolute maximum: 38)
numeric-literal-length:       38

# Maximum number of characters allowed in the character-string (max. 255)
pic-length:                    255

# Default assign type
# Value: 'dynamic', 'external'
assign-clause:                 dynamic

# If yes, file names are resolved at run time using
# environment variables.
# For example, given ASSIGN TO "DATAFILE", the file name will be
# 1. the value of environment variable 'DD_DATAFILE' or
# 2. the value of environment variable 'dd_DATAFILE' or
# 3. the value of environment variable 'DATAFILE' or
# 4. the literal "DATAFILE"
# If no, the value of the assign clause is the file name.
#
filename-mapping:              yes
```

```

# Alternate formatting of numeric fields
pretty-display:                yes

# Allow complex OCCURS DEPENDING ON
complex-odo:                    no

# Allow REDEFINES to other than last equal level number
indirect-redefines:            no

# Binary byte size - defines the allocated bytes according to PIC
# Value:      signed  unsigned  bytes
#            -----  -
# '2-4-8'     1 - 4    same      2
#             5 - 9    same      4
#             10 - 18  same      8
#
# '1-2-4-8'   1 - 2    same      1
#             3 - 4    same      2
#             5 - 9    same      4
#             10 - 18  same      8
#
# '1--8'      1 - 2    1 - 2     1
#             3 - 4    3 - 4     2
#             5 - 6    5 - 7     3
#             7 - 9    8 - 9     4
#             10 - 11  10 - 12    5
#             12 - 14  13 - 14    6
#             15 - 16  15 - 16    7
#             17 - 18  17 - 18    8
#
binary-size:                    1-2-4-8

# Numeric truncation according to ANSI
binary-truncate:                yes

# Binary byte order
# Value: 'native', 'big-endian'
binary-byteorder:               big-endian

# Allow larger REDEFINES items
larger-redefines-ok:            no

# Allow certain syntax variations (eg. REDEFINES position)
relax-syntax-checks:            no

# Allow zero length reference-modification
# (only checked with active EC-BOUND-REF-MOD)
ref-mod-zero-length:            yes

# Perform type OSVS - If yes, the exit point of any currently
# executing perform is recognized if reached.
perform-osvs:                    no

```

```
# Compute intermediate decimal results like IBM OSVS
arithmetic-osvs:          no

# MOVE like IBM (mvc); left to right, byte by byte
move-ibm:                no

# SELECT RELATIVE KEY and ASSIGN fields must be in WORKING-STORAGE
select-working:         no

# LOCAL-STORAGE SECTION implies RECURSIVE attribute
local-implies-recursive: no

# If yes, LINKAGE SECTION items remain allocated
# between invocations.
sticky-linkage:         no

# If yes, allow non-matching level numbers
relax-level-hierarchy:  no

# If yes, evaluate constant expressions at compile time
constant-folding:      yes

# Allow Hex 'F' for NUMERIC test of signed PACKED DECIMAL field
hostsign:              no

# If yes, set WITH UPDATE clause as default for ACCEPT dest-item,
# except if WITH NO UPDATE clause is used
accept-update:         no

# If yes, set WITH AUTO clause as default for ACCEPT dest-item,
# except if WITH TAB clause is used
accept-auto:          no

# If yes, DISPLAYs and ACCEPTs are, by default, done on the CRT (i.e., using
# curses).
console-is-crt:       no

# If yes, allow redefinition of the current program's name. This prevents its
# use in a prototype-format CALL/CANCEL statement.
program-name-redefinition: yes

# If yes, NO ECHO/NO-ECHO/OFF is the same as SECURE (hiding input with
# asterisks, not spaces).
no-echo-means-secure: no

# If yes, the first item in a field screen ACCEPT/DISPLAY (e.g. DISPLAY x UPON
# CRT) is located after the previous ACCEPT/DISPLAY (as though LINE 0 COL 0 had
# been specified).
line-col-zero-default: yes

# If yes, DISPLAY SPACES acts as ERASE EOS, DISPLAY X"01" acts as ERASE EOL,
```

```

# DISPLAY X"02" acts as BLANK SCREEEN and DISPLAY X"07" acts as BELL. Note
# DISPLAY LOW-VALUE is excluded from this; it will always just position the
# cursor.
display-special-fig-consts:      no

# If yes, COMP-1 is a signed 16-bit integer and any PICTURE clause is ignored.
binary-comp-1:                  no

# If yes, POINTER is handled as BINARY-DOUBLE UNSIGNED instead of its own class
numeric-pointer:                no

# auto-adjust to zero like MicroFocus does
move-non-numeric-lit-to-numeric-is-zero: no

# If yes, implicitly define a variable for an ASSIGN DYNAMIC which does not
# match an existing data item.
implicit-assign-dynamic-var:    yes

# What rules to apply to SCREEN SECTION items clauses
screen-section-rules:           gc

# Whether DECIMAL-POINT IS COMMA has effect in XML/JSON GENERATE
dpc-in-data:                    xml

# Dialect features
# Value: 'ok', 'warning', 'archaic', 'obsolete', 'skip', 'ignore', 'error',
#       'unconformable'

alter-statement:                obsolete
comment-paragraphs:            obsolete
call-overflow:                 archaic
data-records-clause:           obsolete
debugging-mode:               ok
use-for-debugging:            ok
listing-statements:           skip      # may be a user-defined word
title-statement:              skip      # may be a user-defined word
entry-statement:              ok
goto-statement-without-name:   obsolete
label-records-clause:         obsolete
memory-size-clause:          obsolete
move-noninteger-to-alphanumeric: error
move-figurative-constant-to-numeric: archaic
move-figurative-space-to-numeric: error
move-figurative-quote-to-numeric: obsolete
multiple-file-tape-clause:    obsolete
next-sentence-phrase:        archaic
odo-without-to:              warning
padding-character-clause:     obsolete
section-segments:            ignore
stop-literal-statement:      obsolete
stop-identifier-statement:   obsolete
same-as-clause:              ok

```

```

type-to-clause:                ok
usage-type:                    ok
synchronized-clause:          ok
special-names-clause:         ok
top-level-occurs-clause:      ok
value-of-clause:              obsolete
numeric-boolean:              ok
hexadecimal-boolean:          ok
national-literals:            ok
hexadecimal-national-literals: ok
national-character-literals:  warning

acu-literals:                  unconformable
hp-octal-literals:            unconformable
word-continuation:            warning
not-exception-before-exception: ok
accept-display-extensions:    ok
renames-uncommon-levels:     ok
symbolic-constant:           ok
constant-78:                  ok
constant-01:                  ok
perform-varying-without-by:   ok
reference-out-of-declaratives: warning
program-prototypes:           ok
call-convention-mnemonic:     ok
call-convention-linkage:      ok
numeric-value-for-edited-item: ok
incorrect-conf-sec-order:     ok
define-constant-directive:    archaic
free-redefines-position:      warning
records-mismatch-record-clause warning
record-delimiter:             ok
sequential-delimiters:        ok
record-delim-with-fixed-recs: ok
missing-statement:           warning
zero-length-literals:        ok
xml-generate-extra-phrases:   ok
continue-after:               ok
goto-entry:                   warning
assign-variable:              ok
assign-using-variable:        ok
assign-ext-dyn:               ok
assign-disk-from:             ok
vsam-status:                  ignore

# use complete word list; synonyms and exceptions are specified below
reserved-words:                default

# not-reserved:
# Value: Word to be taken out of the reserved words list
not-reserved:                  TERMINAL
# reserved:

```

```
# Entries of the form word-1=word-2 define word-1 as an alias for default
# reserved word word-2. No spaces are allowed around the equal sign.
reserved:      AUTO-SKIP=AUTO
reserved:      AUTOTERMINATE=AUTO
reserved:      BACKGROUND-COLOUR=BACKGROUND-COLOR
reserved:      BEEP=BELL
reserved:      BINARY-INT=BINARY-LONG
reserved:      BINARY-LONG-LONG=BINARY-DOUBLE
reserved:      CELLS=CELL
reserved:      COLOURS=COLORS
reserved:      EMPTY-CHECK=REQUIRED
reserved:      EQUALS=EQUAL
reserved:      FOREGROUND-COLOUR=FOREGROUND-COLOR
reserved:      HIGH-VALUES=HIGH-VALUE
reserved:      INITIALISE=INITIALIZE
reserved:      INITIALISED=INITIALIZED
reserved:      LENGTH-CHECK=FULL
reserved:      LOW-VALUES=LOW-VALUE
reserved:      ORGANISATION=ORGANIZATION
reserved:      PIXELS=PIXEL
reserved:      SYNCHRONISED=SYNCHRONIZED
reserved:      TIMEOUT=TIME-OUT
reserved:      VALUES=VALUE
reserved:      ZEROES=ZERO
reserved:      ZEROS=ZERO
```

## Appendix G Module loader cobcrun options

The following list of options was extracted from `cobcrun --help` and shows all available options for the module loader with a short description.

- `-h, -help`  
display this help and exit
- `-V, -version`  
display cobcrun and runtime version and exit
- `-i, -info`  
display runtime information (build/environment)
- `-v, -verbose`  
display extended output with `-info`
- `-c file, -config=file`  
set runtime configuration from *file*
- `-r, -runtime-config`  
display current runtime configuration (value and origin for all settings)
- `-M module, -module=module`  
set entry point module name and/or load path where `-M module` prepends any directory to the dynamic link loader library search path and any basename to the module preload list (`COB_LIBRARY_PATH` and/or `COB_PRELOAD`)

## Appendix H Runtime configuration

The following list was extracted from `config/runtime.cfg`.

### H.1 General instructions

The initial `runtime.cfg` file is found in the `$COB_CONFIG_DIR` , which defaults to `installdir/gnucobol/config` (see `cobcrun --info` for the local path that is configured). The environment variable `COB_RUNTIME_CONFIG` may define a different runtime configuration file to read.

If settings are included in the runtime environment file multiple times then the last setting value is used, no warning occurs.

Settings via environment variables always take precedence over settings that are given in runtime configuration files. And the environment is checked after completing processing of the runtime configuration file(s)

All values set to string variables or environment variables are checked for `{envvar}` and replacement is done at the time of the setting. You can also specify a default value for the case that `envvar` is not set: `{envvar:default}` (the format `{envvar:-default}` is supported, too).

Any environment variable may be set with the directive `setenv .`

Example `setenv COB_LIBARAY_PATH ${LD_LIBRARY_PATH}`

Any environment variable may be unset with the directive `unsetenv` (one var per line).

Example `unsetenv COB_LIBRARAY_PATH`

Runtime configuration files can `include` other files with the directive `include .`

Example `include my-runtime-configuration-file`

To `include` another configuration file only if it is present use the directive `includeif .` You can also use `{envvar}` inside this.

Example `includeif ${HOME}/mygc.cfg`

If you want to reset a parameter to its default value use `reset parametername .`

Most runtime variables have boolean values, some are switches, some have string values, integer values (if not explicit noted: unsigned) and some are size values. The boolean values will be evaluated as following: to true: 1, Y, ON, YES, TRUE (no matter of case) to false: 0, N, OFF.

A `size` value is an unsigned integer optionally followed by 'K', 'M', or 'G' for 'kilo', 'mega' or 'giga'.

For convenience a parameter in the `runtime.cfg` file may be defined by using either the environment variable name or the parameter name. In most cases the environment variable name is the parameter name (in upper case) with the prefix `COB_ .`

For a complete list of the settings in use see `cobcrun --runtime-config .`

Note: If you want to *slightly* speed up a program's startup time, remove all of the comments from the actual real configuration file that is processed.

## H.2 General environment

Environment name: COB\_DISABLE\_WARNINGS  
 Parameter name: disable\_warnings  
 Purpose: turn off runtime warning messages  
 Type: boolean  
 Default: false  
 Example: DISABLE\_WARNINGS TRUE

Environment name: COB\_ENV\_MANGLE  
 Parameter name: env\_mangle  
 Purpose: names checked in the environment would get non alphanumeric change to '\_'  
 Type: boolean  
 Default: false  
 Example: ENV\_MANGLE TRUE

Environment name: COB\_SET\_DEBUG  
 Parameter name: debugging\_mode  
 Purpose: to enable USE ON DEBUGGING procedures that were active during compile-time because of WITH DEBUGGING MODE, otherwise the code generated will be skipped  
 Type: boolean  
 Default: false  
 Example: COB\_SET\_DEBUG 1

Environment name: COB\_SET\_TRACE  
 Parameter name: set\_trace  
 Purpose: to enable COBOL trace feature  
 Type: boolean  
 Default: false  
 Example: SET\_TRACE TRUE

Environment name: COB\_TRACE\_FILE  
 Parameter name: trace\_file  
 Purpose: to define where COBOL trace output should go  
 Type: string : \$\$ is replaced by process id  
 Note: file is opened for append if name starts with "+"  
 Default: stderr  
 Example: TRACE\_FILE \${HOME}/mytrace.\$\$

Environment name: COB\_TRACE\_FORMAT  
 Parameter name: trace\_format  
 Purpose: to define format of COBOL trace output  
 Type: string  
 Default: "%P %S Line: %L"  
 %P is replaced by Program-Id/Function-Id minimal length 29 with prefix  
 %I is replaced by Program-Id/Function-Id variable length,

```

        without prefix
        %L is replaced by Line number, right justified, length 6
        %S is replaced by statement type and name
        %F is replaced by source file name
Example: TRACE_FORMAT "Line: %L %S"
Note:    format of GC2.2 and older:
        "PROGRAM-ID: %I      Line: %L      %S"

Environment name: COB_STACKTRACE
Parameter name:  stracktrace
Purpose:        to disable stracktrace creation on abort
Type:          boolean
Default:       true
Example:       STRACKTRACE no

Environment name: COB_DUMP_FILE
Parameter name:  dump_file
Purpose:        to define where COBOL dump output should go
Note:          the -fdump=all compile option prepares for dump;
               file is opened for append if name starts with "+"
Type:          string      : $$ is replaced by process id
Default:       stderr
Example:       DUMP_FILE  ${HOME}/mytrace.log

Environment name: COB_DUMP_WIDTH
Parameter name:  dump_width
Purpose:        to define COBOL dump line length
Type:          integer
Default:       100
Example:       dump_width 120

Environment name: COB_CURRENT_DATE
Parameter name:  current_date
Purpose:        specify an alternate Date/Time to be returned to ACCEPT
               clauses this is used for testing purposes or to tweak
               a missing offset partial setting is allowed
Type:          numeric string in format YYYYDDMMHH24MISS or date string
Default:       the operating system date is used
Example:       COB_CURRENT_DATE "2016/03/16 16:40:52"
               current_date YYYYMMDDHHMMSS+01:00

@section Call environment
@verbatim

Environment name: COB_LIBRARY_PATH
Parameter name:  library_path
Purpose:        paths for dynamically-loadable modules
Type:          string
Note:          the default paths ./installpath/extras are always
               added to the given paths

```

Example: LIBRARY\_PATH /opt/myapp/test:/opt/myapp/production

Environment name: COB\_PRE\_LOAD

Parameter name: pre\_load

Purpose: modules that are loaded during startup, can be used to CALL COBOL programs or C functions that are part of a module library

Type: string

Note: the modules listed should NOT include extensions, the runtime will use the right ones on the various platforms, COB\_LIBRARY\_PATH is used to locate the modules

Example: PRE\_LOAD COBOL\_function\_library:external\_c\_library

Environment name: COB\_LOAD\_CASE

Parameter name: load\_case

Purpose: resolve ALL called program names to UPPER or LOWER case

Type: Only use UPPER or LOWER

Default: if not set program names in CALL are case sensitive

Example: LOAD\_CASE UPPER

Environment name: COB\_PHYSICAL\_CANCEL

Parameter name: physical\_cancel

Purpose: physically unload a dynamically-loadable module on CANCEL, this frees some RAM and allows the change of modules during run-time but needs more time to resolve CALLs (both to active and not-active programs)

Alias: default\_cancel\_mode, LOGICAL\_CANCEL (0 = yes)

Type: boolean (evaluated for true only)

Default: false

Example: PHYSICAL\_CANCEL TRUE

### H.3 File I/O

Environment name: COB\_VARSEQ\_FORMAT

Parameter name: varseq\_format

Purpose: declare format used for variable length sequential files  
 - different types and lengths precede each record  
 - 'length' is the data length, does not include the prefix

Type: 0 means 2 byte record length (big-endian) + 2 NULs

1 means 4 byte record length (big-endian)

2 means 4 byte record length (local machine int)

3 means 2 byte record length (big-endian)

Default: 0

Example: VARSEQ\_FORMAT 1

Environment name: COB\_FILE\_PATH

Parameter name: file\_path

Purpose: define default location where data files are stored

Type: file path directory  
Default: . (current directory)  
Example: FILE\_PATH \${HOME}/mydata

Environment name: COB\_LS\_FIXED  
Parameter name: ls\_fixed  
Purpose: Defines if LINE SEQUENTIAL files should be fixed length (or variable, by removing trailing spaces)  
Alias: STRIP\_TRAILING\_SPACES (0 = yes)  
Type: boolean  
Default: false  
Example: LS\_FIXED TRUE

Environment name: COB\_LS\_NULLS  
Parameter name: ls\_nulls  
Purpose: Defines for LINE SEQUENTIAL files what to do with data which is not DISPLAY type. This could happen if a LINE SEQUENTIAL record has BINARY/COMP data fields in it.  
Type: boolean  
Default: false  
Note: The TRUE setting will insert a null character x"00" before those values to escape them, and redo on read-in.  
Example: LS\_NULL = TRUE

Environment name: COB\_SYNC  
Parameter name: sync  
Purpose: Should the file be synced to disk after each write/update  
Type: boolean  
Default: false  
Example: SYNC: TRUE

Environment name: COB\_SORT\_MEMORY  
Parameter name: sort\_memory  
Purpose: Defines how much RAM to assign for sorting data if this size is exceeded the SORT will be done on disk instead of memory  
Type: size but must be more than 1M  
Default: 128M  
Example: SORT\_MEMORY 64M

Environment name: COB\_SORT\_CHUNK  
Parameter name: sort\_chunk  
Purpose: Defines how much RAM to assign for sorting data in chunks  
Type: size but must be within 128K and 16M  
Default: 256K  
Example: SORT\_CHUNK 1M

## H.4 Screen I/O

Environment name: COB\_BELL  
Parameter name: bell  
Purpose: Defines how a request for the screen to beep is handled  
Type: FLASH, SPEAKER, FALSE, BEEP  
Default: BEEP  
Example: BELL SPEAKER

Environment name: COB\_REDIRECT\_DISPLAY  
Parameter name: redirect\_display  
Purpose: Defines if DISPLAY output should be sent to 'stderr'  
Type: boolean  
Default: false  
Example: redirect\_display Yes

Environment name: COB\_SCREEN\_ESC  
Parameter name: screen\_esc  
Purpose: Enable handling of ESC key during ACCEPT  
Type: boolean  
Default: false  
Note: is only evaluated if COB\_SCREEN\_EXCEPTIONS is active  
Example: screen\_esc Yes

Environment name: COB\_SCREEN\_EXCEPTIONS  
Parameter name: screen\_exceptions  
Purpose: enable exceptions for function keys during ACCEPT  
Type: boolean  
Default: false  
Example: screen\_exceptions Yes

Environment name: COB\_TIMEOUT\_SCALE  
Parameter name: timeout\_scale  
Purpose: specify translation in milliseconds for ACCEPT clauses  
BEFORE TIME value / AFTER TIMEOUT  
Type: integer  
0 means 1000 (Micro Focus COBOL compatible), 1 means 100  
(ACUCOBOL compatible), 2 means 10, 3 means 1  
Default: 0  
Note: the minimum and possible maximum value depend on the  
screenio library used  
Example: timeout\_scale 3

Environment name: COB\_INSERT\_MODE  
Parameter name: insert\_mode  
Purpose: specify default insert mode for ACCEPT; 0=off, 1=on  
Type: boolean  
Default: false  
Note: also sets the cursor type (if available)  
Example: insert\_mode Y

Environment name: COB\_MOUSE\_FLAGS  
Parameter name: mouse\_flags

Purpose: specify which mouse events will be sent as function key to the application during ACCEPT and how they will be handled

Type: int (by bits)

Default: 1

Note: 0 disables the mouse cursor, any other value enables it, any value containing 1 will enable internal handling (click to position, double-click to enter).  
See copy/screenio.cpy for list of events and their values.

Alias: MOUSE\_FLAGS

Example: 11 (enable internal handling => 1, left press => 2, double-click => 8; 1+2+8=11)

Environment name: COB\_MOUSE\_INTERVAL

Parameter name: mouse\_interval

Purpose: specifies the maximum time (in thousands of a second) that can elapse between press and release events for them to be recognized as a click.

Type: int (0 - 166)

Default: 100

Note: 0 disables the click resolution (instead press + release are recognized), also disables positioning by mouse click

Environment name: COB\_DISPLAY\_PRINT\_PIPE

Parameter name: display\_print\_pipe

Purpose: Defines command line used for sending output of DISPLAY UPON PRINTER to (via pipe)  
This is very similar to Micro Focus COBPRINTER

Note: Each executed DISPLAY UPON PRINTER statement causes a new invocation of command-line (= new process start).  
Each invocation receives the data referenced in the DISPLAY statement and is followed by an end-of-file condition.  
COB\_DISPLAY\_PRINT\_FILE, if set, takes precedence over COB\_DISPLAY\_PRINT\_PIPE.

Alias: COBPRINTER

Type: string

Default: not set

Example: print 'cat >>/tmp/myprt.log'

Environment name: COB\_DISPLAY\_PRINT\_FILE

Parameter name: display\_print\_file

Purpose: Defines file to be appended to by DISPLAY UPON PRINTER

Note: Each DISPLAY UPON PRINTER opens, appends and closes the file.

Type: string : \$\$ is replaced by process id

Default: not set

Example: display\_printer '/tmp/myprt.log'

Environment name: COB\_DISPLAY\_PUNCH\_FILE

Parameter name: display\_punch\_file

Purpose: Defines file to be created on first DISPLAY UPON SYSPUNCH/SYSPCH

Note: The file will be only be closed on runtime exit.  
Type: string : \$\$ is replaced by process id  
Default: not set  
Example: display\_punch './punch\_\$\$out'

Environment name: COB\_LEGACY  
Parameter name: legacy  
Purpose: keep behavior of former runtime versions, currently only for setting screen attributes for non input fields  
Type: boolean  
Default: not set  
Example: legacy true

Environment name: COB\_EXIT\_WAIT  
Parameter name: exit\_wait  
Purpose: to wait on main program exit if an extended screenio DISPLAY was issued without an ACCEPT following  
Type: boolean  
Default: true  
Example: COB\_EXIT\_WAIT off

Environment name: COB\_EXIT\_MSG  
Parameter name: exit\_msg  
Purpose: string to display if COB\_EXIT\_WAIT is processed, set to '' if no actual display but an ACCEPT should be done  
Type: string  
Default: 'end of program, please press a key to exit' (localized)  
Example: COB\_EXIT\_MSG ''

## H.5 Report I/O

Environment name: COB\_COL\_JUST\_LRC  
Parameter name: col\_just\_lrc  
Purpose: If true, then COLUMN defined as LEFT, RIGHT or CENTER will have the data justified within the field limits  
If false, then the data is just copied into the column as is  
Type: boolean  
Default: TRUE  
Example: col\_just\_lrc True

# Appendix I GNU Free Documentation License

Version 1.3, 3 November 2008

Copyright © 2000, 2001, 2002, 2007, 2008 Free Software Foundation, Inc.

<https://fsf.org/>

Everyone is permitted to copy and distribute verbatim copies of this license document, but changing it is not allowed.

## 0. PREAMBLE

The purpose of this License is to make a manual, textbook, or other functional and useful document *free* in the sense of freedom: to assure everyone the effective freedom to copy and redistribute it, with or without modifying it, either commercially or noncommercially. Secondly, this License preserves for the author and publisher a way to get credit for their work, while not being considered responsible for modifications made by others.

This License is a kind of “copyleft”, which means that derivative works of the document must themselves be free in the same sense. It complements the GNU General Public License, which is a copyleft license designed for free software.

We have designed this License in order to use it for manuals for free software, because free software needs free documentation: a free program should come with manuals providing the same freedoms that the software does. But this License is not limited to software manuals; it can be used for any textual work, regardless of subject matter or whether it is published as a printed book. We recommend this License principally for works whose purpose is instruction or reference.

## 1. APPLICABILITY AND DEFINITIONS

This License applies to any manual or other work, in any medium, that contains a notice placed by the copyright holder saying it can be distributed under the terms of this License. Such a notice grants a world-wide, royalty-free license, unlimited in duration, to use that work under the conditions stated herein. The “Document”, below, refers to any such manual or work. Any member of the public is a licensee, and is addressed as “you”. You accept the license if you copy, modify or distribute the work in a way requiring permission under copyright law.

A “Modified Version” of the Document means any work containing the Document or a portion of it, either copied verbatim, or with modifications and/or translated into another language.

A “Secondary Section” is a named appendix or a front-matter section of the Document that deals exclusively with the relationship of the publishers or authors of the Document to the Document’s overall subject (or to related matters) and contains nothing that could fall directly within that overall subject. (Thus, if the Document is in part a textbook of mathematics, a Secondary Section may not explain any mathematics.) The relationship could be a matter of historical connection with the subject or with related matters, or of legal, commercial, philosophical, ethical or political position regarding them.

The “Invariant Sections” are certain Secondary Sections whose titles are designated, as being those of Invariant Sections, in the notice that says that the Document is released under this License. If a section does not fit the above definition of Secondary then it is not allowed to be designated as Invariant. The Document may contain zero Invariant Sections. If the Document does not identify any Invariant Sections then there are none.

The “Cover Texts” are certain short passages of text that are listed, as Front-Cover Texts or Back-Cover Texts, in the notice that says that the Document is released under this License. A Front-Cover Text may be at most 5 words, and a Back-Cover Text may be at most 25 words.

A “Transparent” copy of the Document means a machine-readable copy, represented in a format whose specification is available to the general public, that is suitable for revising the document straightforwardly with generic text editors or (for images composed of pixels) generic paint programs or (for drawings) some widely available drawing editor, and that is suitable for input to text formatters or for automatic translation to a variety of formats suitable for input to text formatters. A copy made in an otherwise Transparent file format whose markup, or absence of markup, has been arranged to thwart or discourage subsequent modification by readers is not Transparent. An image format is not Transparent if used for any substantial amount of text. A copy that is not “Transparent” is called “Opaque”.

Examples of suitable formats for Transparent copies include plain ASCII without markup, Texinfo input format, LaTeX input format, SGML or XML using a publicly available DTD, and standard-conforming simple HTML, PostScript or PDF designed for human modification. Examples of transparent image formats include PNG, XCF and JPG. Opaque formats include proprietary formats that can be read and edited only by proprietary word processors, SGML or XML for which the DTD and/or processing tools are not generally available, and the machine-generated HTML, PostScript or PDF produced by some word processors for output purposes only.

The “Title Page” means, for a printed book, the title page itself, plus such following pages as are needed to hold, legibly, the material this License requires to appear in the title page. For works in formats which do not have any title page as such, “Title Page” means the text near the most prominent appearance of the work’s title, preceding the beginning of the body of the text.

The “publisher” means any person or entity that distributes copies of the Document to the public.

A section “Entitled XYZ” means a named subunit of the Document whose title either is precisely XYZ or contains XYZ in parentheses following text that translates XYZ in another language. (Here XYZ stands for a specific section name mentioned below, such as “Acknowledgements”, “Dedications”, “Endorsements”, or “History”.) To “Preserve the Title” of such a section when you modify the Document means that it remains a section “Entitled XYZ” according to this definition.

The Document may include Warranty Disclaimers next to the notice which states that this License applies to the Document. These Warranty Disclaimers are considered to be included by reference in this License, but only as regards disclaiming warranties: any other implication that these Warranty Disclaimers may have is void and has no effect on the meaning of this License.

## 2. VERBATIM COPYING

You may copy and distribute the Document in any medium, either commercially or noncommercially, provided that this License, the copyright notices, and the license notice saying this License applies to the Document are reproduced in all copies, and that you add no other conditions whatsoever to those of this License. You may not use technical measures to obstruct or control the reading or further copying of the copies you make or distribute. However, you may accept compensation in exchange for copies. If you distribute a large enough number of copies you must also follow the conditions in section 3.

You may also lend copies, under the same conditions stated above, and you may publicly display copies.

## 3. COPYING IN QUANTITY

If you publish printed copies (or copies in media that commonly have printed covers) of the Document, numbering more than 100, and the Document’s license notice requires Cover Texts, you must enclose the copies in covers that carry, clearly and legibly, all these Cover Texts: Front-Cover Texts on the front cover, and Back-Cover Texts on the back cover. Both

covers must also clearly and legibly identify you as the publisher of these copies. The front cover must present the full title with all words of the title equally prominent and visible. You may add other material on the covers in addition. Copying with changes limited to the covers, as long as they preserve the title of the Document and satisfy these conditions, can be treated as verbatim copying in other respects.

If the required texts for either cover are too voluminous to fit legibly, you should put the first ones listed (as many as fit reasonably) on the actual cover, and continue the rest onto adjacent pages.

If you publish or distribute Opaque copies of the Document numbering more than 100, you must either include a machine-readable Transparent copy along with each Opaque copy, or state in or with each Opaque copy a computer-network location from which the general network-using public has access to download using public-standard network protocols a complete Transparent copy of the Document, free of added material. If you use the latter option, you must take reasonably prudent steps, when you begin distribution of Opaque copies in quantity, to ensure that this Transparent copy will remain thus accessible at the stated location until at least one year after the last time you distribute an Opaque copy (directly or through your agents or retailers) of that edition to the public.

It is requested, but not required, that you contact the authors of the Document well before redistributing any large number of copies, to give them a chance to provide you with an updated version of the Document.

#### 4. MODIFICATIONS

You may copy and distribute a Modified Version of the Document under the conditions of sections 2 and 3 above, provided that you release the Modified Version under precisely this License, with the Modified Version filling the role of the Document, thus licensing distribution and modification of the Modified Version to whoever possesses a copy of it. In addition, you must do these things in the Modified Version:

- A. Use in the Title Page (and on the covers, if any) a title distinct from that of the Document, and from those of previous versions (which should, if there were any, be listed in the History section of the Document). You may use the same title as a previous version if the original publisher of that version gives permission.
- B. List on the Title Page, as authors, one or more persons or entities responsible for authorship of the modifications in the Modified Version, together with at least five of the principal authors of the Document (all of its principal authors, if it has fewer than five), unless they release you from this requirement.
- C. State on the Title page the name of the publisher of the Modified Version, as the publisher.
- D. Preserve all the copyright notices of the Document.
- E. Add an appropriate copyright notice for your modifications adjacent to the other copyright notices.
- F. Include, immediately after the copyright notices, a license notice giving the public permission to use the Modified Version under the terms of this License, in the form shown in the Addendum below.
- G. Preserve in that license notice the full lists of Invariant Sections and required Cover Texts given in the Document's license notice.
- H. Include an unaltered copy of this License.
- I. Preserve the section Entitled "History", Preserve its Title, and add to it an item stating at least the title, year, new authors, and publisher of the Modified Version as given on the Title Page. If there is no section Entitled "History" in the Document, create one stating the title, year, authors, and publisher of the Document as given on its

Title Page, then add an item describing the Modified Version as stated in the previous sentence.

- J. Preserve the network location, if any, given in the Document for public access to a Transparent copy of the Document, and likewise the network locations given in the Document for previous versions it was based on. These may be placed in the “History” section. You may omit a network location for a work that was published at least four years before the Document itself, or if the original publisher of the version it refers to gives permission.
- K. For any section Entitled “Acknowledgements” or “Dedications”, Preserve the Title of the section, and preserve in the section all the substance and tone of each of the contributor acknowledgements and/or dedications given therein.
- L. Preserve all the Invariant Sections of the Document, unaltered in their text and in their titles. Section numbers or the equivalent are not considered part of the section titles.
- M. Delete any section Entitled “Endorsements”. Such a section may not be included in the Modified Version.
- N. Do not retitle any existing section to be Entitled “Endorsements” or to conflict in title with any Invariant Section.
- O. Preserve any Warranty Disclaimers.

If the Modified Version includes new front-matter sections or appendices that qualify as Secondary Sections and contain no material copied from the Document, you may at your option designate some or all of these sections as invariant. To do this, add their titles to the list of Invariant Sections in the Modified Version’s license notice. These titles must be distinct from any other section titles.

You may add a section Entitled “Endorsements”, provided it contains nothing but endorsements of your Modified Version by various parties—for example, statements of peer review or that the text has been approved by an organization as the authoritative definition of a standard.

You may add a passage of up to five words as a Front-Cover Text, and a passage of up to 25 words as a Back-Cover Text, to the end of the list of Cover Texts in the Modified Version. Only one passage of Front-Cover Text and one of Back-Cover Text may be added by (or through arrangements made by) any one entity. If the Document already includes a cover text for the same cover, previously added by you or by arrangement made by the same entity you are acting on behalf of, you may not add another; but you may replace the old one, on explicit permission from the previous publisher that added the old one.

The author(s) and publisher(s) of the Document do not by this License give permission to use their names for publicity for or to assert or imply endorsement of any Modified Version.

## 5. COMBINING DOCUMENTS

You may combine the Document with other documents released under this License, under the terms defined in section 4 above for modified versions, provided that you include in the combination all of the Invariant Sections of all of the original documents, unmodified, and list them all as Invariant Sections of your combined work in its license notice, and that you preserve all their Warranty Disclaimers.

The combined work need only contain one copy of this License, and multiple identical Invariant Sections may be replaced with a single copy. If there are multiple Invariant Sections with the same name but different contents, make the title of each such section unique by adding at the end of it, in parentheses, the name of the original author or publisher of that section if known, or else a unique number. Make the same adjustment to the section titles in the list of Invariant Sections in the license notice of the combined work.

In the combination, you must combine any sections Entitled “History” in the various original documents, forming one section Entitled “History”; likewise combine any sections Entitled “Acknowledgements”, and any sections Entitled “Dedications”. You must delete all sections Entitled “Endorsements.”

## 6. COLLECTIONS OF DOCUMENTS

You may make a collection consisting of the Document and other documents released under this License, and replace the individual copies of this License in the various documents with a single copy that is included in the collection, provided that you follow the rules of this License for verbatim copying of each of the documents in all other respects.

You may extract a single document from such a collection, and distribute it individually under this License, provided you insert a copy of this License into the extracted document, and follow this License in all other respects regarding verbatim copying of that document.

## 7. AGGREGATION WITH INDEPENDENT WORKS

A compilation of the Document or its derivatives with other separate and independent documents or works, in or on a volume of a storage or distribution medium, is called an “aggregate” if the copyright resulting from the compilation is not used to limit the legal rights of the compilation’s users beyond what the individual works permit. When the Document is included in an aggregate, this License does not apply to the other works in the aggregate which are not themselves derivative works of the Document.

If the Cover Text requirement of section 3 is applicable to these copies of the Document, then if the Document is less than one half of the entire aggregate, the Document’s Cover Texts may be placed on covers that bracket the Document within the aggregate, or the electronic equivalent of covers if the Document is in electronic form. Otherwise they must appear on printed covers that bracket the whole aggregate.

## 8. TRANSLATION

Translation is considered a kind of modification, so you may distribute translations of the Document under the terms of section 4. Replacing Invariant Sections with translations requires special permission from their copyright holders, but you may include translations of some or all Invariant Sections in addition to the original versions of these Invariant Sections. You may include a translation of this License, and all the license notices in the Document, and any Warranty Disclaimers, provided that you also include the original English version of this License and the original versions of those notices and disclaimers. In case of a disagreement between the translation and the original version of this License or a notice or disclaimer, the original version will prevail.

If a section in the Document is Entitled “Acknowledgements”, “Dedications”, or “History”, the requirement (section 4) to Preserve its Title (section 1) will typically require changing the actual title.

## 9. TERMINATION

You may not copy, modify, sublicense, or distribute the Document except as expressly provided under this License. Any attempt otherwise to copy, modify, sublicense, or distribute it is void, and will automatically terminate your rights under this License.

However, if you cease all violation of this License, then your license from a particular copyright holder is reinstated (a) provisionally, unless and until the copyright holder explicitly and finally terminates your license, and (b) permanently, if the copyright holder fails to notify you of the violation by some reasonable means prior to 60 days after the cessation.

Moreover, your license from a particular copyright holder is reinstated permanently if the copyright holder notifies you of the violation by some reasonable means, this is the first time you have received notice of violation of this License (for any work) from that copyright holder, and you cure the violation prior to 30 days after your receipt of the notice.

Termination of your rights under this section does not terminate the licenses of parties who have received copies or rights from you under this License. If your rights have been terminated and not permanently reinstated, receipt of a copy of some or all of the same material does not give you any rights to use it.

#### 10. FUTURE REVISIONS OF THIS LICENSE

The Free Software Foundation may publish new, revised versions of the GNU Free Documentation License from time to time. Such new versions will be similar in spirit to the present version, but may differ in detail to address new problems or concerns. See <https://www.gnu.org/licenses/>.

Each version of the License is given a distinguishing version number. If the Document specifies that a particular numbered version of this License “or any later version” applies to it, you have the option of following the terms and conditions either of that specified version or of any later version that has been published (not as a draft) by the Free Software Foundation. If the Document does not specify a version number of this License, you may choose any version ever published (not as a draft) by the Free Software Foundation. If the Document specifies that a proxy can decide which future versions of this License can be used, that proxy’s public statement of acceptance of a version permanently authorizes you to choose that version for the Document.

#### 11. RELICENSING

“Massive Multiauthor Collaboration Site” (or “MMC Site”) means any World Wide Web server that publishes copyrightable works and also provides prominent facilities for anybody to edit those works. A public wiki that anybody can edit is an example of such a server. A “Massive Multiauthor Collaboration” (or “MMC”) contained in the site means any set of copyrightable works thus published on the MMC site.

“CC-BY-SA” means the Creative Commons Attribution-Share Alike 3.0 license published by Creative Commons Corporation, a not-for-profit corporation with a principal place of business in San Francisco, California, as well as future copyleft versions of that license published by that same organization.

“Incorporate” means to publish or republish a Document, in whole or in part, as part of another Document.

An MMC is “eligible for relicensing” if it is licensed under this License, and if all works that were first published under this License somewhere other than this MMC, and subsequently incorporated in whole or in part into the MMC, (1) had no cover texts or invariant sections, and (2) were thus incorporated prior to November 1, 2008.

The operator of an MMC Site may republish an MMC contained in the site under CC-BY-SA on the same site at any time before August 1, 2009, provided the MMC is eligible for relicensing.

## ADDENDUM: How to use this License for your documents

To use this License in a document you have written, include a copy of the License in the document and put the following copyright and license notices just after the title page:

Copyright (C) *year* *your name*.

Permission is granted to copy, distribute and/or modify this document under the terms of the GNU Free Documentation License, Version 1.3 or any later version published by the Free Software Foundation; with no Invariant Sections, no Front-Cover Texts, and no Back-Cover Texts. A copy of the license is included in the section entitled ‘‘GNU Free Documentation License’’.

If you have Invariant Sections, Front-Cover Texts and Back-Cover Texts, replace the ‘‘with...Texts.’’ line with this:

with the Invariant Sections being *list their titles*, with the Front-Cover Texts being *list*, and with the Back-Cover Texts being *list*.

If you have Invariant Sections without Cover Texts, or some other combination of the three, merge those two alternatives to suit the situation.

If your document contains nontrivial examples of program code, we recommend releasing these examples in parallel under your choice of free software license, such as the GNU General Public License, to permit their use in free software.